



 *ISS45 System Maintenance
and Utilities
Version 7.1.4.0*

ISS45 System Maintenance and Utilities

Date of Issue	Product Identification Number	Part Number	Brief Description
August 1995	45001/001	80316774	Version 7.1
October 1995	45001/001	80316201	Version 7.2
October 1996	45001/001	80328018	Version 7.3
February 1999	45001/001	80602997	Version 7.6
August 2000	45001/050	89000071	Separate Document
July 2001	45001/050	89000071	Fujitsu covers
August 2003	45001/073	89000144	Version 7.8
July 2005	45001/050	89000245	Version 7.10
April 2007	45001/050	89000355	Version 7.1.2.0
July 2008	45001/050	89000468	Version 7.1.3.0
November 2010	45001/050	89000601	Version 7.1.4.0

© Copyright StoreNext Retail Technologies LLC 1995-2010
All rights reserved

This publication is protected by federal copyright law. No part of this publication may be reproduced or transmitted into any human or computer language in any form or by any means, stored in a retrieval system, transmitted, redistributed, translated or disclosed to third parties, or de-compiled in any way including, but not limited to, photocopy, photograph, electronic, mechanical, magnetic or manual without the express written permission of StoreNext Retail Technologies LLC or its licensors, if any. All copies, so authorized, shall contain a full copy of this copyright notice.

StoreNext Retail Technologies LLC endeavors to ensure that the information in this document is correct and fairly stated but does not accept liability for any error or omission. StoreNext Retail Technologies LLC makes no representation or warranties with respect to the contents hereof, and specifically disclaims any implied warranties of merchantability or fitness for a particular purpose or non-infringement. No commitments by StoreNext or its suppliers are made from this documentation which is provided for information only.

Development of StoreNext products and documentation is continuous: StoreNext Retail Technologies LLC reserves the right to revise this publication and to make changes from time to time in the contents hereof or in the products herein described or discussed without notice and without any obligation of StoreNext Retail Technologies LLC to notify any person or organization of such revision or changes. Information published in this document will likely become obsolete over time and it is recommended that users regularly check for updates and newer versions.

StoreNext Retail Technologies LLC has prepared this manual for use by users, authorized third parties and personnel of StoreNext Retail Technologies LLC as a guide to the proper installation, operation, customization and/or maintenance of StoreNext Retail Technologies LLC equipment and software. The drawings and specifications contained herein are the property of StoreNext Retail Technologies LLC and/or its licensors.

Third-party products, services, or company names referenced in this document may be trademarked or copyrighted by their respective owners, and are for identification purposes only.

Copyrights, trademarks and license agreements shall be governed and construed in accordance with the laws of the State of Texas and the Federal Arbitration Act, and shall benefit Retailix, its successors, and assigns.

Address comments and corrections to:

StoreNext Retail Technologies LLC
Software Program Director
6100 Tennyson Parkway
Suite 130
Plano, Texas 75024

Table of Contents

Table of Contents.....	1
System Maintenance and Utilities.....	6
Accessing System Maintenance & Utilities Options	6
System Parameters.....	6
Setting System Parameters.....	7
Back Office Parameters	7
General Back Office Parameters - Page 1	9
PCs in System.....	11
Printer Settings.....	12
Printers in System	13
Printer Control Strings	14
End of Day - Page 1	16
End of Day - Page 2	18
End of Day - Page 3	19
End of Day - Page 4 and 5	22
EOD Job Stream Reports - Page 1	23
EOD Job Stream Reports - Page 2	24
EOD Job Stream Reports - Page 3	25
EOD Job Stream Reports - Page 4	25
Cashier Office Parameters - Page 1	26
Cashier Office Parameters - Page 2	29
PLUs and Items - Page 1	30
PLUs and Items - Page 2	34
PLU and Promotion Batches	36
Windows NT Add-Ons.....	41
Report Parameters Page 1.....	44
Code Distribution Management.....	46
Code Management Parameters	46
RSession Parameters	48
Package Status Maintenance.....	49

Blackout Periods	49
POST Parameters 1	51
General POST Parameters 1	51
General POST Parameters 2	55
General POST Parameters 3	58
General POST Parameters 4	61
Sign On/Off, Secure	64
WIC Options	67
Tax, Food Stamp Options	70
Frequent Shopper Options	72
Discount, Account Options	77
Control Check Options 1	78
Control Check Options 2	80
Var. Price/Weight Item Codes 1	83
Var. Price/Weight Item Codes 2	84
Restricted Sale Birthday Validation	85
Restricted Sale Layouts	87
Restricted Sale Times	89
Restricted Sale Special Dates	90
Tare Weight Parameters (1-30)	90
% Tare Weight Parameters (31-60)	92
Signs	92
WIC CVV Options	94
POST Parameters 2	96
Electronic Payment Settings	98
Retailer Information 1-3	99
Retailer Information 4-5	99
POST User Hooks	100
Customer Display Messages	101
Reorganize Receipt	103
Rounding Parameters	107
Member Card and Promotion	108
Member Card	108
Member Promotion	111
Additional Tender Information	113
Barcoded Tender Options	113

Signature Capture Tenders	116
Gift Card Options.....	117
Electronic Check Conversion	119
Biometric Options Parameters	121
FSA Options	123
Trading Stamp Parameters	124
Multiple Stamp Schemes.....	126
Receipt Printing Parameters	128
Q-Buster	132
MobileLime	132
LaneHawk	133
POST Configuration	135
Checkout Bank Groups	144
Coupon Parameters	146
Coupon Parameters 1	148
Coupon Parameters 2	150
Coupon Parameters 3	151
Coupon Parameters 4	154
Coupon Printing Parameters	156
Coupon Printing Maintenance	157
Adding a New Coupon	158
Transaction Handling Parameters	161
Design POS Menus	164
POS Closed Menu	165
Adding a new menu option	165
Cost Plus Programming	168
CDV Programming	169
Adding/updating a new CDV scheme.....	170
Service Fee Programming.....	170
System Integrity.....	172
QDX Files Checksum Table	175
Software Key Information	177
Poll List Program.....	177
Receipt Header/Footer Maintenance	179
Defining a New Header/Footer	180

Defining a header	180
Defining a footer	181
Updating a Header/Footer	182
Linking a Header/Footer to POS	183
Security Maintenance.....	183
Users Password Definition	184
Changing User Status	186
Updating a User	186
Printing a Users List	187
Users Inquiry	187
System Security Levels	187
Assigning System Security Levels	188
User Access Log	190
Selecting a File	191
By User.....	192
By Description	192
Record/Playback Keys	193
CCTV Interface.....	196
LAN Monitoring	197
Freeze	197
Clear Screen	198
Active keys	198
Debug.....	198
Watch File	198
LAN Comm.....	199
Date and Time.....	199
CCMS LOG	201
Field Engineer's Utilities.....	201
QuickDex Definition	202
Convert 7.X Files to 7.3 Files	210
Build PLU File from Comm. File	211
Compare and Rebuild Mix & Match File.....	212
Compare and Rebuild POST PLU File	213
Build Audit Seq File	214
Unzip PLU File	214

POS Keyboard Programming.....	215
Function Maintenance	215
Program Keys.....	218
Updating a Keyboard Layout.....	225
Link POS to Keyboard	227
Electronic Journal.....	229
Electronic Journal - Search Facility	229
Electronic Journal - Supervisor Authorizations.....	229
POST Graphics	229
Graphic Logo Maintenance	230
Screen Saver Setup	232
System Alerts	235
Alerts Log	236
Selecting a File.....	237
Searching for Alerts.....	238
Sorting	238
Display all Records.....	239
Printing	239
Alert Types Maintenance.....	239
Adding a New Alert.....	241
Updating an Alert Type.....	242
Deleting an Alert Type	243
Printing an Alerts Type List	243
Alerts Parameters.....	244
Run POS Application (PIP)	245
Index	246

System Maintenance and Utilities

The System Maintenance & Utilities option provides access to the system parameters, to various maintenance programs and to ISS45 utilities.

Accessing System Maintenance & Utilities Options

- To access a System Maintenance & Utilities option
 - 1 From the main menu, select System Maintenance & Utilities. The Maintenance & Utilities menu displays.




- 2 From the Maintenance & Utilities menu, select the required option. The relevant option screen displays.

System Parameters

The System Parameters option provides access to various parameters that enable you to customize back-office, terminal and an assortment of other operations.

To access this option, select System Parameters from the Maintenance & Utilities menu. The System Parameters menu displays.



Setting System Parameters

System parameter settings are entered in one of the following ways:

- Entering a value in the field space. For example, the number of decimal positions, the size of a file, or a file name.
- Checking the parameter by pressing the *Space Bar*. The check sign appears within the square brackets: [✓]. To uncheck such a parameter, press the *Space Bar* again. The check sign clears.
- Selecting a value from a drop-down list. When [↓] appears on the parameter line, press the *Right Arrow* to open the list. Highlight the required option using the *Up Arrow* and *Down Arrow*, and press *Enter* to select it.


Back Office Parameters

The Back Office Parameters option enables you to customize the system for your store. These parameter settings provide the system with such information as:

- The date format and decimal position to use.

- The unit of measurement to be used for weight.
- Names, record lengths and locations of some files.
- Whether or not some of the system features are being used. For example, Delayed Cashier Balancing, Enhanced Cashier/Store Balancing, Subdepartment classification, etc.
- When and how to execute batch files.
- Specific file record sizes.
- Which End of Day reports to print.
- When to perform End of Day, End of Month and End of Year procedures.

To access the Back Office Parameters option, select Back Office Parameters from the System Parameters menu. The Back Office Parameters menu displays.



The Back Office Parameters option provides access to further options, each with their own parameter screen(s). The parameters are described, option by option, in the following pages. Some parameter options have more than one screen of parameters. To move from one screen to another, use *F6* (Next Page) and *F5* (Previous Page). After you set parameters on a screen, press *F2* to record them.

General Back Office Parameters - Page 1

To access this option, select General Back Office Parameters from the Back Office Parameters menu. The following screen displays.

```

PCM
Ver 7.8.3.0020  TIM'S MARKETS  PC# 01 MFS1
General Back Office Parameters Page 01
1. Store name.....TIM'S MARKETS
2. Store number.....00000
3. Store VAT number.....100
4. Date: American or European.....American [↓]
5. Decimal point position [0-3]: 0=x,,1=.x etc.....2
6. Pounds or kilograms weight.....Pounds [↓]
7. Subdepartment in system.....[N]
8. Allow customer accounts maintenance.....[N]
9. Megabytes remaining on disk to initiate a warning message.....50
10. Factura in system.....[N]
11. Use department tax exclusive sales for Weekly Business Report..[ ]
12. Skip store number check digit validation on enhanced bad acct..[N]
13. Prohibit user sign on at more than one server simultaneously...[ ]
14. User defined DOS batch file name.....
15. Run DOS batch automatically every 3 x 15 seconds.....
16. When Screen Saver starts, system will exit to.....Previous Menu [↓]

[F2] Update

07/09/2003 08:42:41 Copyright Fujitsu-ICL Inc.
  
```


Parameter	Description
Store Name	Enter the name of your store (up to 28 characters). This name displays on all screens and reports.
Store Number	Enter the code number of your store (up to five digits - up to 65000)).
Store VAT Number	Store's VAT registration number.
Date: American or European	Select the date format to be used in your system: American or European. The American date format is MMDDYY. The European date format is DDMMYY.
Decimal Point Position	The number of positions (up to three) to the right of the decimal point. 0 means no decimal points.
Pounds or Kilograms Weight	Select the unit of measurement used in your POS terminals: Pounds or Kilograms.

Parameter	Description
Subdepartment in System	Check this parameter to enable item classification by subdepartments. For more explanations, see the chapter 'Subdepartment Maintenance'.
Megabytes Remaining on Disk to Initiate a Warning Message	Enter the minimum free disk space required (in megabytes). When the disk space on your computer is less than this amount, a warning message displays.
Factura in System	A sales receipt may be printed in invoice format. Check this parameter to allow this option. The cashier is then prompted to choose the invoice option, before the sales receipt is printed.
Use Department Tax Exclusive Sales for Weekly Business Report	Check this parameter if you want department sales to be printed without tax. (Only used where the tax system in use is tax <i>inclusive</i> .)
Skip Store Number Check Digit Validation on Enhanced Bad Acct.	If you want the system to validate the store number check digit in the Enhanced Bad Accounts program, leave this parameter unchecked. To skip validation, check this parameter.
Prohibit User Sign-On at more than One Server Simultaneously	If you want to allow users to sign-on at only one server at a time, check this parameter.
User defined DOS batch file name	Name the specific DOS batch file. Note This DOS batch file will run in background mode and will only be executed if the user is in a main menu and if there is no alert message present.
Run DOS batch automatically every --- x15 seconds	This parameter enables you to run your own DOS batch file with time intervals. This enhancement gives you the option to run any user defined DOS batch file (not for PLU or Promotion batch files). Insert the number to be multiplied by fifteen seconds. This calculation determines the interval period (in seconds) between batch files to be executed.

Parameter	Description
When Screen Saver Starts, system will exit to	Select either one of the following from the drop down list: • None • Prev. Menu • Sign on Screen

PCs in System

To access this option, select PCs in System from the Back Office Parameters menu. The following screen displays.




Parameter	Description
PC Number 1 (MFS1) in System	Check this parameter if MFS1 exists in the configuration.
PC Number 2 (MFS2) in System	Check this parameter if MFS2 exists in the configuration.

Parameter	Description
PC Number 3-10 (Workstation) in System	If PCs other than MFS1 and MFS2 are connected to the system, check the corresponding parameter. For example, if there are two more computers, check the PC Number 3 and PC Number 4 parameters. Indicate whether you wish to reboot the workstation during End of Day by placing a checkmark in the corresponding checkbox.

Printer Settings

To access the options Printers in System and Printer Control Strings, select Printers Settings from the Back Office Parameters menu. The following screen displays.



Printers in System

To access this option, select Printer Settings, Printers in System from the Back Office Parameters menu. The following screen displays.

PC Number	Printer Type	LPT
MFS1	HP Laser (PCL 5) - Letter	LPT 1
MFS2	HP Laser (PCL 5) - Letter	LPT 1
LFS3	Dot Matrix	LPT 1
LFS4	Dot Matrix	LPT 1
LFS5	Dot Matrix	LPT 1
LFS6	Dot Matrix	LPT 1
LFS7	Dot Matrix	LPT 1
LFS8	Dot Matrix	LPT 1
LFS9	Dot Matrix	LPT 1
LFS10	Dot Matrix	LPT 1


[F2] Update

07/07/2003 08:48:18 Copyright Fujitsu-ICL Inc.

Parameter	Description
LPT for PC Number 1 (MFS1)	Select the applicable LPT number for MFS1 from the drop-down list. - LPT 1 - LPT 2
LPT for PC Number 2 (MFS2)	Select the applicable LPT number for MFS2 (if it exists in this configuration), from the drop-down list. - LPT 1 - LPT 2
LPT for PC Number 3-10 (Workstation) in System	If PCs other than MFS1 and MFS2 are connected to the system, check the applicable LPT number for each workstation.

Printer Control Strings

To access this option, select Printer Settings from the Back Office Parameters menu. The following screen displays.



In Printer Control Strings, the *setup* button allows you to select between HP Laser – A4 and HP Laser – Letter.

Each printer setting adds at least four types of control strings to the printer. You must add at least one of them depending on the printer type chosen in 'Printers in System'.


Printer Settings allows you to differentiate between printing two types of reports: those sent directly to the printer and those sent first to a file and then to the printer.

Example 1:

When a report is sent directly to the printer, IPM checks whether the PC is connected to a laser printer or dot matrix. If laser printing is set up, it sends the escape sequence matching the report format, followed by the report and the reset escape sequence.

Example 2:

When a report is sent to file, it may be printed on any type of printer. IPM places a special character at the beginning of the report. This character tells IPM to send the appropriate escape sequence.



Parameter	Description
Number	Printer number.
Description	Enter in the name of the printer.
Action	Check this to make the current setting active.
Lines/page	Enter in the number of lines to print per page.
Printer types	Select the printer type from the drop down list.
Line text mode	Select the line text mode from the drop down list.
Control string	Enter any required ESC characters and sequences.

End of Day - Page 1

To access this option, select End of Day from the Back Office Parameters menu. The following screen displays.

Parameter	Value
1. Allow E-O-D activation from a workstation.....	[]
2. Build credit ASCII file during E-O-D.....	[N]
3. Credit ASCII file name.....	seq\credit.seq
4. Build an ASCII transaction file during E-O-D.....	[N]
5. Send Pay Path totals during E-O-D.....	[]
6. Allow changing of trading date, next trading date, EOD type.....	[N]
7. Days to keep Electronic Journal transactions history.....	30

Parameter	Description
Allow E-O-Day Activation from a Workstation	Check this parameter if the store uses a remote workstation, and you want to be able to activate End of Day from it.
Note You cannot activate Automatic End of Day from a workstation.	
Build Credit ASCII File during E-O-D	Builds an ASCII file of all credit-based transactions.
Credit File ASCII Name	The default name is credit.seq, in the \seq directory.

Parameter	Description
Build an ASCII Transaction File during E-O-D	Check this option if you want an ASCII transaction file to be built during End of Day. This file is created in addition to the regular transaction file. The file for each day is saved in the \HISTORY directory, and is named, for example, AS960423.ZIP. The prefix is always AS, followed by the date.
Send Pay Path totals during E-O-D	Not used.
Allow changing of trading date, next trading date, EOD type	Check this option to allow changing of the trading date, next trading date and EOD type (Day, Week, Month, Year) when EOD is initiated.
Days to keep Electronic Journal transaction history	Enter the number of days to keep transaction history within the Electronic Journal. The default is 30.

Select *F6* to move to the next page.

End of Day - Page 2

ISS PCM Ver 7.8.3.0020 TIM'S MARKETS PC# 01 MFS1

End of Day Parameters Page 02

1.	Day of the week to perform end-of-week.....	?
2.		
3.	Day in the month to perform end-of-month for January.....	31
4.	Day in the month to perform end-of-month for February.....	28
5.	Day in the month to perform end-of-month for March.....	31
6.	Day in the month to perform end-of-month for April.....	30
7.	Day in the month to perform end-of-month for May.....	31
8.	Day in the month to perform end-of-month for June.....	30
9.	Day in the month to perform end-of-month for July.....	31
10.	Day in the month to perform end-of-month for August.....	31
11.	Day in the month to perform end-of-month for September.....	30
12.	Day in the month to perform end-of-month for October.....	31
13.	Day in the month to perform end-of-month for November.....	30
14.	Day in the month to perform end-of-month for December.....	31
15.		
16.	Day and month to perform end-of-year.....[mm/dd].....	12/31
17.	Day in week to perform weekly item movement <0 = regular EOW>.	0

[F2] Update [F5] Prev Page [F6] Next Page

07/09/2003 13:10:02 Copyright Fujitsu-ICL Inc.

This screen contains parameters for scheduling End of Day procedures.

End of Day is a daily procedure that processes the data accumulated in the store during that day. In addition, End of Day performs end of week, end of month and end of year operations, to sum up the activities of the current week, current month and current year. The day of the week for performing an End of Day procedure, the day in the month for performing an End-of-Month procedure for each month of the year, and the day and month for performing an End of Year are determined via the parameters on this screen.

When the user activates the End of Day option, a screen displays the type of procedure to perform, based on the days defined via these parameters. However, the user can request to run these procedures on other days. For further explanations, see the chapter 'End of Day'.

For each parameter, enter the day to perform the stated function:

- Day of the Week to Perform End-of-Week. For example, 1 for Sunday, 2 for Monday, etc.
- Day in the Month to Perform End-of-Month for January through December. For example, 31 for January, etc.

- Day and Month to Perform End-of-Year (month and day in mm/dd format). For example, 12/31 for December 31.
- Day in the week to perform weekly item movement. For example, 1 for Sunday, 2 for Monday, etc. A "0" directs the weekly item movement to be performed on the same day as the end-of-week.

Select *F6* to move to the next page.

End of Day - Page 3

Ver 7.8.3.0020 TIM'S MARKETS PC# 01 MFS1

End of Day Parameters Page 03

1. 24 hours trading store.....[1]

2. Minutes to wait for POS to send remaining transactions.....90

3. PC number to activate automatic E-O-D.....MFS1 [↓]

	Sun	Mon	Tue	Wed	Thu	Fri	Sat
Automatic	[]	[]	[]	[]	[]	[]	[]
Time	09:26	11:57	15:55	12:28	10:15	12:00	13:24

Note: Define exceptional EOD dates on next page.

[F2] Update [F5] Prev Page [F6] Next Page

07/09/2003 13:18:54 Copyright Fujitsu-ICL Inc.

This screen contains parameters for setting 24-hour and Automatic End of Day procedures.

Notes on Automatic End of Day

- When Automatic End of Day is run while a cashier is signed on, the current transaction will be saved on the next day's date.
- That part of the transaction created before the POS terminal enters End of Day is sent to the Back Office marked as 'bad' on the next day's date.
- No checksum on QDX files is performed. The POS terminal files are therefore not compared with those on the Back Office.
- The POS terminal does not save the local transaction file.
- There is no loading of QDX files.

- Cashier totals remain unchanged.

Set up the appropriate End of Day settings with the parameters in the following table.

Parameter	Description
24 Hours Trading Store	Check to indicate your store operates around the clock. This option allows you to run End of Day (manually or automatically) even when cashiers are signed on at the POS terminals and serving customers. A [PC_EOD] message at the bottom of the cashier screen informs cashiers that End of Day is running 'This prompt later changes to [OFFLINE] while the MFS reboots. Cashiers can continue serving with no affect on performance. End of Day reports do not print at the POS terminal during this End of Day process.
Minutes to Wait for POS to Send Remaining Transactions (For Automatic End of Day only)	Enter the minutes for the MFS to wait, after it has started End of Day, to receive transactions from the POS terminals, as well as send maintenance updates. Once the indicated number of minutes is passed, the MFS continues the End of Day process on the terminals.
PC Number to Activate Automatic E-O-D	Select the appropriate option from the drop-down list. • None - No Automatic End of Day • MFS1 • MFS2

Note

You must select MFS1 or MFS2 to activate Automatic End of Day.

The first time you use this option, you must also update the current working date in the Date and Time option.

Parameter	Description
Automatic: Sunday through Saturday	Press the <i>Space Bar</i> to check each day of the week you want to run Automatic End of Day. You may want to run End of Day manually on specific days. Just leave the required days unchecked. Note If the next working day is a holiday, use the parameters on the next two screens to define a different (exceptional) working date.
Time: Sunday through Saturday	Enter the required time to initiate End of Day for each day of the week.

If you need to define exceptional dates, where the next working dates are holidays, select *F6* to move to the next page.

End of Day - Page 4 and 5

ISS PCM
Ver 7.8.3.0020 TIM'S MARKETS PC# 01 MFS1
End Of Day Parameters Page 04

Exceptional dates for automatic end of day:

Date	N.W. Date	Date	N.W. Date	Date	N.W. Date
01/01/1980	01/01/1980	01/01/1980	01/01/1980	01/01/1980	01/01/1980
01/01/1980	01/01/1980	01/01/1980	01/01/1980	01/01/1980	01/01/1980
01/01/1980	01/01/1980	01/01/1980	01/01/1980	01/01/1980	01/01/1980
01/01/1980	01/01/1980	01/01/1980	01/01/1980	01/01/1980	01/01/1980
01/01/1980	01/01/1980	01/01/1980	01/01/1980	01/01/1980	01/01/1980

<N.W. Date = Next working date>

[F2] Update [F5] Prev Page [F6] Next Page

07/09/2003 13:21:53 Copyright Fujitsu-ICL Inc.

This screen (and the next) each contain 15 date fields for scheduling exceptional dates for the next working date. You would normally use this option to indicate the next working date after a holiday.

We recommend that the system administrator set up these dates ahead of time, for a year. They can, of course, be changed at any time to suit the required circumstances.

- In the Date fields, enter the required exceptional EOD dates.
- Enter the specific next working dates required, in the N.W. Date fields.

Select F2 to save the setup.

EOD Job Stream Reports - Page 1

This feature allows the user to specify which End of Day reports to generate and which reports to print. It is not necessary to generate and print all reports.

Check the reports you wish to print at EOD. To print a report, set both the Generate and the Print check boxes. If only the print field is set, the report will not be generated and therefore will not print at EOD.

If only the generate field is set, the report is generated during EOD and may be viewed in EOD History Reports.

To access this option, select EOD Job Stream Reports from the Back Office Parameters menu. The following screen displays.

Report Name	Generate	Print
1. Control report.....	☐	☐
2. Post Report (Grand total) report.....	☐	☐
3. Media report.....	☐	☐
4. Hourly Productivity report.....	☐	☐
5. Fifteen Minutes Productivity report.....	☐	☐
6. Department report.....	☐	☐
7. Expanded Department report.....	☐	☐
8. Weekly Expanded Department report.....	☐	☐
9. Monthly Expanded Department report.....	☐	☐
10. Yearly Expanded Department report.....	☐	☐
11. Department by Cashier report.....	☐	☐
12. Department by Terminal report.....	☐	☐
13. Department by Hour report.....	☐	☐
14. Department by Customer report.....	☐	☐
15. Department Information report.....	☐	☐
16. Traders Sales report.....	☐	☐

[F2] Update [F6] Next Page

07/09/2003 13:41:48 Copyright Fujitsu-ICL Inc.

This screen contains parameters to specify which reports to generate during the End of Day procedure. Check the relevant reports.

Select *F6* to move to the next screen.

EOD Job Stream Reports - Page 2

ISS PCM Ver 7.8.3.0020 TIM'S MARKETS PC# 01 MFS1 EOD Job Stream Reports Page 02

	Generate	Print
1. Department VAT report.....	☐	☐
2. Group Sales report.....	☐	☒
3. Promotion Add/Loss report.....	☐	☐
4. Sort Promotion Add/Loss report by ID.....	☐	☐
5. Sort Promotion Add/Loss report by Department.....	☐	☐
6. Sale Items Add/Loss report.....	☐	☐
7. Sort Sale Item Add/Loss report by Department.....	☐	☐
8. Payout/ROA reports.....	☐	☐
9. Cashier Performance report.....	☐	☐
10. Cashier Productivity by Hour report.....	☐	☐
11. Daily Operator Performance report.....	☐	☐
12. Weekly Operator Performance report.....	☐	☐
13. Monthly Operator Performance report.....	☐	☐
14. Branch Performance report.....	☐	☐
15. Daily Refunds report.....	☐	☐
16. Period Refunds report.....	☐	☐

[F2] Update [F5] Prev Page [F6] Next Page

07/09/2003 13:42:35 Copyright Fujitsu-ICL Inc.

This screen contains additional parameters to specify which reports to generate and optionally print during the End of Day procedure.

Check the Sort Promotion Add/Loss Report by Department and Sort Sale Item Add/Loss Report by Department parameters, if these End of Day reports should be sorted by department.

Select F6 to move to the next screen.

Parameter	Description
Sort Promotion Add/Loss report by ID	Select this option if you want the Promotion Add/Loss report sorted by ID.

Note

Ensure the following:
 Promotion Add/Loss Report in EOD Job Stream Reports (page 2) must be set to 'Generate' and 'Print'. Sort Promotion Add/Loss Report by Department in EOD Job Stream Reports (page 2) must not be set to 'Generate' and 'Print'.

EOD Job Stream Reports - Page 3

PCM
 Ver 7.8.3.0020 TIM'S MARKETS PC# 01 MFS1
EOD Job Stream Reports Page 03

	Generate	Print
1. Department Flash Sales & Sales Mix report.....	[X]	[]
2. Net Department Sales Flash report.....	[X]	[]
3. Statement Of Trade Receivables report.....	[X]	[]
4. Cashier History report.....	[X]	[]
5. POS Sales report.....	[X]	[]
6. Saved Transactions report.....	[X]	[]
7. Location report.....	[X]	[]
8. Item Member Promotions Sales report.....	[X]	[]
9. Queue Length Weekly Summary.....	[X]	[]
10. Itemized Check report by Cashier.....	[X]	[]
11. Itemized Check report by POST.....	[X]	[]
12. Vendor Coupon totals report.....	[X]	[]
13. EFT Authorized Transactions report.....	[X]	[X]
14. Trading stamps distribution report.....	[X]	[X]
15. Media in POSTs signed-on at store close report.....	[X]	[X]
16. Audit report - PLU changes.....	[X]	[X]

[F2] Update [F5] Prev Page [F6] Next Page

07/09/2003 13:43:27 Copyright Fujitsu-ICL Inc.

This screen contains additional parameters to specify which reports to generate and optionally print during the End of Day procedure.

EOD Job Stream Reports - Page 4

PCM
Ver 7.8.3.0020 TIM'S MARKETS PC# 01 MFS1
EOD Job Stream Reports Page 04

	Generate	Print
1. EOD Error Status Report <for Automatic EOD only>.....	☐	☐
2. Member Promotion Sales Report.....	☐	☐
3. Daily Cashier/POS Transactions File.....	☐	☐
4. Weekly Cashier/POS Transactions File.....	☐	☐
5. Subtract and Cancel Report.....	☐	☐
6. Daily Reward Checks Report.....	☐	☐
7. Not-Found PLU Report.....	☐	☐
8. Post Checkout Banks report:.....	☐	☐
include banks: ☐ 1 ☐ 2 ☐ 3 ☐ 4 ☐ 5 ☐ 6 ☐ 7 ☐ 8 ☐ 9 ☐ 10		
9. Training Report.....	☐	☐

[F2] Update [F5] Prev Page

07/09/2003 14:54:42 Copyright Fujitsu-ICL Inc.

This screen contains additional parameters to specify which reports to generate and optionally print during the End of Day procedure.

Cashier Office Parameters - Page 1

To access this option, select Cash Office Parameters from the Back Office Parameters menu. The following screen displays.

PCM
Ver 7.8.3.0020 TIM'S MARKETS PC# 01 MFS1
Cash Office Parameters Page 01

1. Allow delayed cashier balancing.....	☐
2. Enhanced Cashier/Store balancing functions.....	☐
3. Delay Cashier/Safe over/short totals.....	☐
4. Allow declarations for cashiers/posts not signed-on in period..	☐
5. Allow transactions <pickups/loans> after cashiers/posts locked..	☐
6. Cashier/POST Locking allowed only to Printer & File or File....	☐
7. Transfer cashier period on End-Of-Week <default is every day>..	☐
8. Do not transfer cashier period on Sunday.....	☐
9. Do not transfer cashier period on Monday.....	☐
10. Do not transfer cashier period on Tuesday.....	☐
11. Do not transfer cashier period on Wednesday.....	☐
12. Do not transfer cashier period on Thursday.....	☐
13. Do not transfer cashier period on Friday.....	☐
14. Do not transfer cashier period on Saturday.....	☐
15. Display current media in till on Cashier/POS Loan/Pickup.....	☐
16.	
17.	
18.	

[F2] Update [F6] Next Page

07/09/2003 15:04:33 Copyright Fujitsu-ICL Inc.


Parameter	Description
Allow Delayed Cashier Balancing Functions	With the Delayed Cashier Balancing feature, the system allows cashiers who work different shifts on different days, to simultaneously retain the totals of both shifts (<i>previous</i> and <i>current</i>), and perform cashier balancing at the end of the second shift. For further explanations, see 'Transfer Current Data to Previous Data', in the 'Cashier Maintenance' chapter. Check this parameter to enable the Delayed Cashier Balancing feature. A cashier will be able to work a current shift before the previous shift's data has been processed or cleared. When you check or clear this parameter, a message box displays with a warning message. This message tells you that before using a cashier function you must empty the CASHIER.QDX and EMPL.QDX files, and create a new cashier file in both MFS1 and MFS2. To do this: 1. Exit to DOS. 2. Type Q-EMPTY 10 11. Press <i>Enter</i>. 3. Create a new cashier file in one of the MFS computers.
Enhanced Cashier/Store Balancing Functions	Check this field to use the Enhanced Cashier/Store Balancing feature. This feature enables the Cashier & Store Balancing option on the Cashier Maintenance menu. This option provides access to several programs for recording cashier and safe transactions, for balancing and zeroing cashier and safe totals, and for generating cashier and store reports. For further explanations on balancing procedures, see "Cash Office Functions" chapter.

Parameter	Description
Delay Cashier/Safe Over/Short Totals	Check this parameter to delay Cashier/Safe over/short totals. Over/short totals are accounted for on the previous days totals.
Allow Declarations for Cashiers/Posts not Signed-on in Period	If checked, allows declarations for cashiers and POS terminals that have not signed-on during the period.
Allow transactions (pickups/loans) after cashiers/posts locked	Allows pickups and loans to be performed even though cashiers or POS Terminals have been locked.
Cashier/POST Locking allowed only to Printer & File or File	Check this to enable cashier/post locking to printer + file or file only. This enhancement disables the Cashier/Post Locking to Printer only option.
Transfer Cashier Period on End of Week (default is every day)	If the store's trading period is a week, check this parameter to transfer cashier totals to the previous period at the end of the week. For example, if a store trades to Sunday, the transfer will be done during End of Week on Sunday night. The system default is to transfer totals at every End of Day.
Do Not Transfer Cashier Period on Sunday through Saturday	To specify which days NOT to transfer cashier periods, check the parameter for the relevant day. This parameter applies only if the above parameter is left blank. That is, the default every day.
Display current media in till on Cashier/POS Loan/Pickup	Check this so that the till quantity and till amount display in the Back Office Loan and Pickup screens. This allows you to compare quantities and amounts of different media types and enables you to do the loan/pickup against the 'expected' amount and quantity in the till.

Select *F6* to move to the next screen.

Cashier Office Parameters - Page 2

The parameters on this page all relate to POS accountability.



Parameter	Description
POS Accountability in System	Check this parameter if your store is working on the basis of POS accountability, and not cashier accountability. Checking this parameter displays a warning (and informative) message. After you check the parameter and press <i>F2</i>, you will have to do the following, in both the MFS1 and MFS2: - Exit to DOS. - Type Q-EMPTY 7 and press <i>Enter</i>. - In one PC create a new poll list.

Warning

The in-safe values will be affected only by POS locking, not cashier locking.

Parameter	Description
Allow Delayed POS Balancing	This parameter affects the system in the same way as Delayed Cashier Balancing. For more information, refer to page 27.
Transfer POS Period on End of Week (default is every day)	If the store's trading period is a week, check this parameter to transfer POS terminal totals to the previous period at the end of the week. For example, if a store trades to Sunday, the transfer will be done during End of Week on Sunday night. The system default is to transfer totals at every End of Day.
Do Not Transfer POS Period on Sunday through Saturday (default is every day)	To specify which days NOT to transfer POS periods, check the parameter for the relevant day. This parameter applies only if the above parameter is left blank. That is, the default every day.
Transfer Balances For Inactive POS	This parameter provides the option to automatically open a new shift for inactive POSs (and transfer balances to the previous period) when Cashier Locking or Transfer Current Data to Previous Period is performed. The default is unchecked (No).
Delay POS/Safe Over/Short Totals	In systems configured for POS Accountability, if this flag is checked over/short totals are accounted for on the previous day's totals.

Note:

When the "Delay POS/Safe Over/Short Totals" parameter is checked, over/short totals are assigned to the previous day's totals in systems where POS Accountability is implemented. The "Allow Delayed POS Balancing" parameter must be enabled to take advantage of this feature.

PLUs and Items - Page 1

To access this option, select PLUs and Items from the Back Office Parameters menu. The following screen displays.

PCM

Ver 7.8.3.0020 TIM'S MARKETS PC# 01 MFS1

PLU and Item Parameters Page 01

1. PLU must have a valid check digit..... []
2. Internal code (item number) in system..... []
3. Update ALL items linked to internal code if one PLU changed.. []
4. CDU scheme for internal code (0=no CDU check).....» 0
5. Mix and Match group maximum value..... 255
6. Update ALL Mix and Match groups if one PLU changed..... []
7. PLU follow department flags as a default..... [X]
8. PLU maintenance audit..... [X]
9. PLU maintenance audit file name..... C:\PCMASTER\SEQ\AUDIT.SEQ
10. Audit file record size..... 128
11. Item includes check digit (for POST)..... []
12. PLU report file name..... c:\pcmaster\seq\plurpt.seq
13. PLU report file record size (minimum 92 bytes)..... 128
14. Profit report file name..... c:\pcmaster\seq\pluprf.seq
15. Profit report file record size (minimum 105 bytes)..... 128
16. Zero price PLU allowed..... [X]
17. Allow Frequent Shopper discount higher than item price..... [X]

[F2] Update [F6] Next Page [F8] List

07/09/2003 15:50:06 Copyright Fujitsu-ICL Inc.

Parameter	Description
PLU must have a Valid Check Digit	Check this parameter if PLU numbers should include check digit verification.
Internal Code (Item Number) in System	If your store uses an internal code (item number), check this parameter. Internal codes are linked to the PLU number. This method can also be used to link many PLU numbers to the same internal code. For example, internal codes for different color toothbrushes can be allocated the same PLU number.
Update ALL Items Linked to Internal Code if one PLU changed	If you are using Internal codes, and several are linked to one PLU, when one item changes, all the linked items change automatically. Details that are affected are: • Department • Price • Frequent Shopper value (discount amount).


Parameter	Description
CDV Scheme for Internal Code (0=no CDV check)	Select the option required, to apply a check digit verification method to internal codes. The options available here are first defined in CDV Programming. See System Parameters.
Mix & Match Group Maximum Value (from 0 to 255)	The maximum mix and match group value to be allowed. Enter a number from 0 to 255. See the Update All Mix & Match Group if One PLU Changed parameter, below.
Update ALL Mix & Match Groups if One PLU Changed	PLU items can be assigned to a Mix & Match Group so that prices can be updated globally by changing the price of a single item in a group. By assigning a Mix & Match code to an item, you can change the price and quantity of all items that are associated to this Mix & Match code. In other words, if you change the price or quantity of an item, you can change all items with the same code. For further explanations, refer to the 'PLU Maintenance' chapter. Check this parameter if the price and quantity of all items with similar mix & match codes should be updated by changing the price or quantity of one of the items. If this parameter is not checked, each price must be individually changed.
PLU Follow Department Flags as a Default	When adding a new PLU item, the parameter values of the department to which the item is assigned can be displayed by default (see the chapter 'PLU Maintenance'). If the store's trading period is a week, check this parameter to transfer cashier totals to the previous period at the end of the week. For example, if a store trades to Sunday, the transfer will be done during End of Week on Sunday night. The system default is to transfer totals at every End of Day.

Parameter	Description
PLU Maintenance Audit	The operations performed in the PLU file (such as new items, updates, price changes, etc.) can be recorded in an audit log file. If you want to maintain such a file, check this parameter, and specify the required file name in the next parameter
PLU Maintenance Audit File Name	Specify the path and name of the PLU maintenance audit file. Use a maximum of eight characters for the filename and three characters for the extension. The default is: C:\PCMASTER\SEQ\AUDIT.SEQ.
Audit File Record Size	Allows you to define the size of the PLU audit file records. Minimum record size is 123 bytes.
Item Includes Check Digit (For POST)	Check this to instruct the POS terminals that items (PLU numbers) include check digit verification.
PLU Report File Name	The PLU Item Report can be printed to a file in your disk (by selecting File as the report destination). This file is created under a directory and file name specified by the PLU Report File Name parameter. The default is C:\PCMASTER\SEQ\PLURPT.SEQ. If you want the report file to be created elsewhere on your disk and/or with a different file name, overwrite the required path and/or name. Use a maximum of eight characters for the filename and three characters for the extension.
PLU Report File Record Size	Enter the PLU report file record size (minimum 92 bytes).

Parameter	Description
Profit Report File Name	The Profitability Report can be printed to a file on your disk (by selecting File as the report destination). This file is created under a directory and file name specified by the Profit Report File Name parameter. The default is C:\PCMASTER\SEQ\PRFRPT.SEQ. If you want the report file to be created elsewhere on your disk and/or with a different file name, overtype the path required and/or name. Up to 8 characters for the filename and 3 characters for the extension.
Profit Report File Record Size	Enter the profitability report file record size (minimum 105 bytes).
Zero Price PLU Allowed	Check this for PLU Maintenance to allow zero-priced items. UPC2 items are allowed to be zero-priced regardless of the parameter.
Allow Frequent Shopper discount higher than item price	Check is field to allow Frequent Shoppers to receive a discount that is higher than the price of the item. If left unchecked, the price of the item is its maximum frequent shopper discount.

Select *F6* to move to the next page.

PLUs and Items - Page 2




Parameter	Description
Set Discount Prohibited Flag to [] if Item is on Sale	If this parameter is checked, when a sale is defined for an item, the Discount Prohibited parameter in the PLU record is automatically checked. When the item returns to its original configuration, the parameter is set back to its original setting.
Set Discount Prohibited Flag to [] if Item is on Promotion	If this parameter is checked, when a promotion is defined for an item, the Discount Prohibited parameter in the PLU record is automatically checked. When the item returns to its original configuration, the parameter is set back to its original setting.
Set Discount Prohibited Flag to [] if Item is on Reduction	If this parameter is checked, when a reduction is defined for an item, the Discount Prohibited parameter in the PLU record is automatically checked. When the item returns to its original configuration, the parameter is set back to its original setting.

Parameter	Description
Set Discount Prohibited Flag to [] if Item is on Offer	If this parameter is checked, when an offer is defined for an item, the Discount Prohibited parameter in the PLU record is automatically checked. When the item returns to its original configuration, the parameter is set back to its original setting.
Zero Sale Weeks Before Actual PLU Local Deletion	Enter the required number of weeks of zero sales, before the system automatically deletes local PLUs from the PLU file. Example: If an item is not sold for, say 13 weeks, the system deletes that item from the PLU file at the end of the 13 week period.
Zero Sale Weeks Before Actual PLU Host Deletion	Enter the required number of weeks of zero sales, before the system automatically deletes host PLUs from the PLU file.
Zero price items change to manual price	Select this option so that the system sets the 'manual price' parameter in PLU record, during the EOD process. If a PLU's price is set to zero on the Back Office, the system will detect this during the End of Day process and will automatically set the Manual Price parameter for the PLU record.
Use ENTER key as the UPC key	Select this option so that when the Enter key is pressed, the check digit for the item will be calculated and entered automatically.

PLU and Promotion Batches

To access this option, select PLU and Promotion Batches from the Back Office Parameters menu. The following screen displays.



Parameter	Description
PLU Batch File Name	The path and name of host batch files. The user can define a different file name to each store, and when the host sends files, only files matching this parameter are executed at this store (XXXX represents the batch number). The default is \PCMASTER\H1XXXX.DAT.
Allow PLU Batch Activation by Date/Time	PLU batch files can be executed automatically at a date and time set by the user. To allow this option, check this parameter. In the PLU Batch Maintenance screen, the system prompts the user for the date and time. For further explanations, see the chapter 'Batch Maintenance'.
Echo Batch PLU Data on Screen	Check this parameter to display the PLU data on the Batch Maintenance screen. Also, if this parameter is checked, the system issues op-code error messages (e.g. item not found) when working with the Batch Maintenance option.

Parameter	Description
Use opcode #1 <new> as INSERT/UPDATE code (Host Files)	This parameter refers to the Batch Code field in the Host Batch File option (see the 'PLU Batch Maintenance' chapter). If checked, when processing a record with code #1 in a batch file, the system treats this record as a new or update record and not just as a new record. If blank, the record is treated as a new record.
Use opcode #2 <update> as INSERT/UPDATE code (Host Files)	This parameter refers to the Batch Code field in the Host Batch File option (see the 'PLU Batch Maintenance' chapter). If checked, when processing a record with code #2 in a batch file, the system treats this record as a new or update record and not just an update record. If blank, the record is treated as an updated record.
PLU Batch Type	Choose from the four options available: • Not defined • Basic (122 bytes) • Enhanced (145 bytes) • Extended (256 bytes): Choose this option to display additional fields in the PLU Batch File screen. With this option, the 'Internal code in System' field always displays in PLU Batch screens.
Use Original Batch Name for Error Batch File	If checked, error files created by batches keep the original file name of the batch. If not checked, error batch files are named 999 (default).

Parameter	Description
Save PLU Batches Before Execution	Depending on how you set this parameter, a PLU batch file is deleted or saved after it successfully executes and updates the PLU file. If you leave this parameter blank, PLU batch files are deleted after execution. If you check this parameter, the PLU batch files are automatically saved, under the PCMASTER directory, as HIXOLD.XXX. The extension XXX contains the old batch number. For further explanations, see 'Executing a Local Batch File', in the chapter 'Batch Maintenance'.
PC Number to Activate Batch Files by Date/Time	Batch files can be automatically activated at the specified date and time, only in one PC. Use this parameter to specify MFS1 or MFS2.
Promotion Batch File Name	The path and name of the promotion batch files. The user can define a different file name to each store, and when the host sends files, only files matching this name are executed at this store (XXXX represents the batch number). The default is C:\PCMASTER\PIXXXX.DAT.
Show PLU Batch description in batch list	Check this parameter to display a PLU Batch description in the main batch list in Local Batch Maintenance. A PLU Batch description may now be entered in the information window, when adding a new batch in Local Batch Maintenance.
Allow Promotion Batch Activation by Date/Time	Promotion batch files can be executed automatically at a date and time set by the user. To allow this option, check this parameter. In the Promotion Batch Maintenance screen, the system will prompt for the date and time. For further explanations, see the chapter 'Promotion Batch Maintenance'.

Parameter	Description
Save Promotion Batches Before Execution	Depending on how you set this parameter, a promotion batch file is deleted or saved after it successfully executes and updates the PLU file. If you leave this parameter blank, the promotion batch files are deleted after execution. If you check this parameter, the promotion batch files are automatically saved, under the PCMASTER directory, as PIXOLD.XXX. The extension XXX contains the old batch number. For further explanations, see 'Executing a Local Batch File', in the chapter 'Promotion Batch Maintenance'.

Windows NT Add-Ons

ISS45 Back Office runs under the Windows NT and Windows 2000 operating systems, taking advantage of its power, speed and security.

The following enhancements have been made to support Windows Operating Systems:

- A red LAN message appears in the upper right corner of the screen if communication between the two servers is down. The check for LAN in the system is done at 30 second intervals.
- There is visual notification to inform you when EOD is running in the background. The message 'E-O-Day in process' appears during EOD.

This screen contains parameters for Personal Computer Communications System (PCCS) and Customer Credit Member Server (CCMS). ISS45 uses the PCCS to receive promotion batch files that are created by the host system. CCMS is a data repository and data mining service. CCMS collects online data of purchases from all registered shoppers. This data may be used for statistical and marketing purposes.

The screenshot shows a configuration window titled 'PCM' with the following content:

```

Ver 7.1.0.0031    TIM'S MARKETS    PC# 01 MFS1
Windows NT Add-Ons

PCCS Parameters
1. PC number to use as PCCS server.....None    [↑↓]

CCMS Parameters
1. Host CCMS type.....Corema    [↑↓]
2. PC number to use as CCMS server.....MFS1    [↑↓]
3. 2nd PC number to use as CCMS server.....None    [↑↓]
4. Port number.....7002
5. CCMS alias in HOSTS file.....COREMA
6. Local CCMS type.....None    [↑↓]

ESL:
1. ESL in system.....[√]

Retailix Pocket Office
1. Action for keyboard functions.....None    [↑↓]
2. Show only alerts from the last.....0 hours
3. RMA Cashier Notification.....[ ]
4. Cashier Notification Icon Time Limit.....0 minutes

[↑↓] Update

07/12/2005    08:40:10    Copyright Fujitsu-ICL Inc.
  
```

Parameter	Description
PC number to use as PCCS server	Select the PC through which two-way information between the store and data warehousing service is to be channeled (e.g., MFS1, MFS2, LFS3).
Host CCMS type	Select the data warehousing service from the following dropdown list: • None • Corema • Fry's VIP Club • MobileLime
PC number to use as CCMS server	Select the PC through which two-way information between the store and data warehousing service is to be channeled (e.g., MFS1, MFS2 or LFS3).
2 nd PC number to use as CCMS Server	Select the PC through which two-way information between the store and data warehousing service is to be channeled, in the event that the primary server fails (e.g., MFS1, MFS2 or LFS3).
Port number	Insert the logical port number which opens the communication socket with the CCMS.
CCMS alias in HOSTS file	Enter a text description of the PC server. The alias must exist in the HOSTS file, in the path: C:\WINNT\SYSTEM32\DRIVERS\ETC. The alias, together with the PC's IP address, is store in the HOST file.
Local CCMS type	Select the appropriate local Customer Card Member Server type.
ESL in system	Set this parameter to Yes to perform internal Unit Pricing calculations for Electronic Shelf Label purposes.

Parameter	Description
Action for Keyboard Functions	This parameter defines how Manager \ Supervisor Authorization requests triggered by keyboard functions are handled from Pocket Office. Click the field's selection arrow and choose: None, Info Only or Allow Approval. Note: While approval at the POS requires entering a supervisor ID and password, authorized approval from the supervisor's HHC is equivalent to performing both steps.
Show Only Alerts From the Last ...Hours	The Pocket Office Remote Authorization Module (RMA) will display only unresolved alerts that were generated in the last X hours that are defined in this parameter.
RMA Cashier Notification	This parameter defines whether the POS displays icons indicating the status of messages sent to Pocket Office.
Cashier Notification Icon Time Limit	This parameter defines the number of minutes before removing a User Request Cashier Notification Icon from the POS display.

Note

When in LAN monitoring, Customer Card Member Server (CCMS) messages are also shown.

RSM and DRVFILE now support a new type of FC message protocol, FC 4A. This FC will be used to handle CCMS messages.

Report Parameters Page 1

ISS PCM

Report Parameters Page 01

1. Exclude Non-merchandise sales from department reports totals..... [Y]
 2. Show cashiers/POS by their sign-on date in Over Short report..... [Y]
 3. Exclude Host batch changes from Audit report..... [Y]

[F2] Update

07/09/2003 21:33:23 Copyright Fujitsu-ICL Inc.


Parameter	Description
Exclude Non-merchandise sales from department reports totals	Select this option so that the system excludes Non-merchandise sales from department report totals. If you select the 'Print Report' option , Non-merchandise sales will print separately for each group of departments. The line "Non Merchandizing Departments sales are not included in the report total" appears at the bottom of each report. The following on-line & EOD reports are modified: • Department Report • Control Report • Expanded Department Reports • Weekly Business Report • Exclusive/Inclusive Sales • Flash Sales & Sales Mix • Net Department Sales Flash • Department VAT

Parameter	Description
Show cashiers/POS by their sign-on date in Over Short report	Select this option to select cashiers (or lanes, if POS Accountability is used) by their sign-on date in the Over/Short Report.
Exclude Host batch changes from Audit Report	Select this option to omit host batches from the Audit Report PLU Changes created during EOD.

Code Distribution Management


Code Distribution is a software application that automatically distributes and performs software upgrades to the POS terminals. Code Distribution enables POS terminals to upgrade automatically when in Sign-off mode. In Sign-on mode, system parameters provide options to enable seamless software upgrades without interfering with normal sales transactions.

An Rsession is a communication channel that supports communication between the MFS1 server, the MFS2 and each POS terminal. Defining Rsession parameters enables Code Distribution software upgrades and prevents overloads in MFS1.



Code Management Parameters

To access this option, select Code Distribution, Code Management parameters from the Back Office Parameters menu. The following screen displays.



Parameter	Description
No. of tickets between retries of upgrade	This parameter specifies the number of sale tickets that can be processed, after which a cashier prompt message will reappear and Code Distribution will retry the POS terminal software upgrade in Sign-on mode.
Max No. of seconds between retries of upgrade	This parameter specifies the interval (in seconds) after which a cashier prompt message will reappear, and Code Distribution will retry the software upgrade.
Max No. of seconds to wait for user confirmation	This parameter specifies the interval (in seconds) that Code Distribution will wait for cashier confirmation before it automatically starts the upgrade.
Max No. of seconds to wait for 2 nd PC Synchronization	Enter the maximum number of seconds that Code Distribution will wait to synchronize the 2 nd PC during the upgrade.

Parameter	Description
Number of months to keep records in PACKAGES.QDX	Enter the months of software upgrade information in the PACKAGES.QDX file.

RSession Parameters

To access this option, select Code Distribution, RSession parameters from the Back Office Parameters menu. The following screen displays.

PCM

Ver 7.8.3.0020 TIM'S MARKETS PC# 01 MFS1

RSession Parameters

1. Rsession active..... []

2. Max No. of tills to upgrade simultaneously from one server..... 0

3. Rsession communication time out..... 0

[F2] Update


07/10/2003 08:52:12 Copyright Fujitsu-ICL Inc.

Parameter	Description
Rsession Active	This parameter enables the Rsession feature and associated parameters. It is recommended to always check the Rsession Active checkbox. Selecting this checkbox ensures that the system will not overload.

Parameter	Description
Max No. of tills to upgrade simultaneously from one server	This parameter specifies the maximum number of POS terminals to upgrade simultaneously. For example, if the store has 20 POS terminals, they may elect to upgrade only 10 POS terminals simultaneously.
Rsession communication time out	This parameter is disabled and will always be set to 0.

Package Status Maintenance

The Package Status Maintenance screen displays code distribution history, the application that automatically distributes and performs software upgrades to the POS terminals.



Blackout Periods

ISS45 can be configured to prevent Code Distribution operations from occurring during designated times on designated days.

Note:

If a CDS process begins on MFS1 before a Blackout Time, the store will continue the upgrade process. If the package cannot run because of a Blackout Time, it will be retried after the next EOD and Alert 2975 (Blackout Period) will be issued.

	<HH:MM>	
	Start	Stop
Monday - Thursday	00:00	00:00
Friday	00:00	00:00
Saturday	00:00	00:00
Sunday	00:00	00:00

Set Valid Days:

Mon	Tue	Wed	Thu	Fri	Sat	Sun
☐	☐	☐	☐	☐	☐	☐

[F2] Update

03/21/2005 08:17:08 Copyright Fujitsu-ICL Inc.


The screen contains the following fields

Parameter	Description
Start	Enter the beginning time (i.e. 23:00 = 11:00 PM) of the range to exclude CDS operations (for the designated day or day range).
Stop	Enter the ending time of the range to exclude CDS operations (for the designated day or day range). After this time CDS can run.
Valid Days	Place a check mark next to the days where the Blackout Period should apply.

POST Parameters 1

This option provides access to various parameters for customizing the POS terminals in your store. POST parameters are initially set by an authorized field engineer, during installation.


To access this option, select POST Parameters 1 from the System Parameters menu. The POST Parameters File 1 menu displays.



Each option on this menu leads to a screen containing a group of parameters. Select the required option to display the parameters screen. Refer to the relevant section below, for parameter descriptions.

General POST Parameters 1

This screen contains general POS terminal parameters.




Parameter	Description
Open Drawer on Tender Purchase	Cash drawer opens on every tender purchase transaction.
Open Drawer in Training Mode	Check this parameter if the cash drawer should be open during transactions that require the cashier to enter media in the drawer, while in Training Mode. If blank, the cash drawer remains closed during the transactions in Training Mode.
Open Drawer on End Of Day	Automatically open the POS terminals' cash drawer when E-O-D begins.

Parameter	Description
Open Drawer Timeout	Defines the number of seconds before the drawer-open alarm sounds.

Parameter	Description
Allow Foreign Currency Change	Check this parameter to allow foreign currency change to be given to a customer. For a transaction that has been overtendered or partially tendered with one or more foreign currency tenders, the cashier has the option to give change in cash, or as any foreign currency in transaction. Refer to the WinPOS User Guide, for more information on foreign currency change.
MSU Rounding Option	This parameter specifies the formula to be used for dividing the price of a multi-item offer among the individual items. For example, in a '3 for \$1.00' offer, instead of charging 33.33 cents for each item, the fraction (.33 cents) is distributed as follows: 34 34 32 or 34 33 33 Select the required formula. With no MSU rounding, the items are broken up into amounts which are close to equal, except that the last item reflects the 'remainder' and usually the smaller value.
Level of Detail on Audit Printer	Check one of the three options: • Minimum: Nothing prints. • Medium: No item details print. • Full: All details print.
Use ENTER Key as Total	Check to use <i>Enter</i> key for Totaling.
PLU/UPC/Enter repeat key in use	Check this parameter to allow the use of these keys.
Department Repeat Key in Use	Check this parameter so that the <Repeat> key can be used to repeat the last department item entry. Refer to the WinPOS User Guide, for more details.

Parameter	Description
Void Tender at Check Signature Allowed	If checked, a tender can be voided when the 'check signature' prompt displays on the POS terminal. 'Check signature' displays if the appropriate parameter in the tender record is checked. If blank, the cashier is not allowed to void a tender during tendering with 'check signature'.
Force Department/Price Entry of Unknown Items	Check this parameter to force cashiers to enter the department and the price of unknown items. (Items not in the system).
Default Minimum Purchase Amount for Promotions	Enter the default minimum purchase amount required before a promotion offer can be given. If a minimum purchase amount is not entered in specific promotion definitions (see the chapter 'Promotion Maintenance'), this amount is considered by default.
Note This parameter does not relate to Member Promotions.	
Second Tender for Payouts/Receipts	Specify an (optional) second tender number for receipts and payouts.
No CDV check on Item Scan/ENTER Key	Specify whether or not the system should perform Check Digit Validation on scanning or manual entry of items.
No UPC5 in System	Check to specify UPC5 functionality not used in the system.
EAN 99 coupon in system	Check to enable EAN 99 coupon functionality
Do not allow sales in tender mode	Check to prohibit sales once tender key is pressed.

General POST Parameters 2



Parameter	Description
Type of Extended Balance Due to Display	Select the type of Extended Balance Due, to display in the bottom half of the customer display. The options are: • None • Food Stamp
Multiple Language in System	Check this option if you have 2 languages set up in your system, and there is a function defined on the POS terminals to switch language.
Reset POS counter during End-of-Day	Check this parameter if you want to reset Transaction numbers to zero with every End of Day.

Parameter	Description
Perform Checksum during End-of-Day	If checked, this process compares the PLU files in the POS terminals to the PLU file on MFS1, during the End of Day procedure. If differences are found, the POSTs are updated after EOD has completed. This process is done in the background, and does not interfere with the operation of the POSTs. Only prices are checked.
	Note
	For more powerful checksum options, see the section on System Integrity.
Always read PLUs from PC	Check this option if you want the POSTs to ignore their own PLU files, and read only from the MFS1 PLU file.
Display F/S total after F/S tender	Check this option to display Food Stamp tender details on the bottom half of the customer display.
Cost Plus in System	Check this parameter if your store operates on a 'Cost-Plus' system. If you check this parameter, you must also set the cost plus ranges and percentages.
Cost Plus Taxable Surcharge Department	The department defined for Cost Plus surcharges.
Cost Plus Non Taxable Surcharge Department	The department defined for non-taxable Cost Plus surcharges.
Charge Payment Tender	The tender number, which must be defined as an in-house charge.
Reversal Charge Payment Tender	The tender number defined for Charge Payment Reversal.
Subtract Cashier Declarations from POS Reports	Check this parameter to deduct cashier declarations from media totals on the POS report. (Not used in USA).
Don't Print POS Reports during End-of-Day	If POS reports are not required to print at End of Day, check this parameter.
Tax report to follow POS report	If checked, the Tax Report prints immediately after the POS Report.

Parameter	Description
Tender for Rounding	Tender number to which rounded amounts are saved. You must first create a tender for rounding. See 'Tender Maintenance'.
Disallow Quantity with Scanning	Don't allow cashier to use QTY button when scanning an item.
Print unique invoice number on charge posting tickets	If checked and a transaction is a Charge Posting transaction, a unique number is printed at the top of all three (multi part) receipts. The thirteen digit unique number is made up of the store number, lane number and transaction number.
Don't print price in PLU group list	If checked, PLU Short Group lists on the PoS terminal show 20 character PLU descriptions and 13 character PLU codes without their prices. If this parameter is not checked, the PoS terminal displays 14 character PLU descriptions and 13 character PLU codes with 4 character prices.

General POST Parameters 3

General Parameters 3:		
1.	Check Guarantee functionality.....	[X]
2.	Times to swipe card before manual entry.....	0
3.	Seconds before credit card number can be entered.....	0
4.	Force ZEROS on coupon number.....	0
5.	Cash in drawer limit.....	500.00
6.	Foodstamps in drawer limit.....	200.00
7.	Maximum number of digits for department value.....	5
8.	Maximum number of digits for media value.....	9
9.	Sales printer sound.....	Always
10.	Supervisor privileges 1.[X] 2.[X] 3.[X] 4.[X] 5.[X] 6.[X] 7.[X] 8.[X]	[X]
11.	In-house account type.....	Charge posting
12.	Password required with cashier bar-code.....	[X]
13.	Suppress Fly Buys check digit on receipt & transaction....	[X]
14.	Prompt for Customer's ID on Save Transaction.....	[X]
15.	Cashier file is resident on POST.....	[X]
16.	Bad Account File is resident on POST.....	[X]
17.	Euro Rate.....	
18.	Key-in Fly Buys number without check digit.....	[]
19.	"Payment amount" prompt defaults to "balance due" amount..	[]

[F21] Update


Parameter	Description
Check Guarantee Functionality	Not implemented.
Times to Swipe Card before Manual Entry (Member Card)	The number of card swipe attempts before cashier is forced to manually key in Member Card account number.
Seconds before Credit Card Number can be Entered (Member Card)	You can set the 'swipe card' prompt to timeout after a set period. This forces manual Member Card account number entry.
Force ZEROS on Coupon Number	This parameter provides the option to force zeros on the coupon number. If you want to force zeros on coupons, specify the number of digits in this parameter. (This parameter is currently not supported).

Parameter	Description
Cash in Drawer Limit	This parameter serves to set a limit for the amount of cash in the POS terminal cash drawer. When this amount is exceeded, a warning sign starts blinking on the terminal display. This sign disappears after performing a cash pick up. This parameter is also used in the Over Limit Cashiers report.
Foodstamps in drawer limit	Enter a Foodstamps in drawer limit. If this limit is exceeded, three flashing asterisks will appear at the top of the POS Terminal screen. (Similar to cash in drawer limit with the three flashing triangles).
Maximum Number of Digits for Department Value	Limit cashier entry of department amounts.
Maximum Number of Digits for Media Value	Limit cashier entry of tender amounts.
Sales Printer Sound	Select the required option. The options are: • None: no beep. • Always: beeps with every item. • Buffer printing: allows buffer printing without the beeps.
Supervisor Privileges, 1 through 8	Not used.
In-house account type	Select the appropriate in-house account type: Charge Posting or Customer Accounts.
Password required with cashier bar-code	Check this parameter in order for the system to request cashier password when signing on with cashier bar-code
Suppress Fly Buys check digit on receipt & transaction	Suppresses printing of Check Digit on receipt and transaction.

Parameter	Description
Prompt for customer's ID on Save Transaction	Check this to enable cashier to enter the customer's ID before saving a transaction. Recalling a transaction can also be done by entering the customer's ID. The customer ID prints on the saved ticket. If cashiers don't want to enter the customer's ID or if the customer does not have ID available, they may select 'No' when prompted. Recall the transaction in three ways: • Enter the Terminal and Ticket numbers • Enter the Customer's ID • Scan the barcode Note Recalling a saved transaction by entering the Customer ID number takes a while longer.
Cashier file is resident on POST	Optionally use this parameter to load the cashier file onto the POS terminals. This provides better control of offline cashier sign-on. When POS terminals are offline, cashier passwords are validated against the cashier file which is resident on the POS Terminal. Notes If you uncheck this option, POS terminals will receive cashier data from the Back Office when cashiers sign on or when supervisor authorization is required. If your store works with the parameter 'System integrity in system', add the EMPL.QDX file to the QDX Files Checksum Table in Field Engineer's Utilities. Loading a large Cashier File onto the POS Terminal takes up memory and can affect performance.

Parameter	Description
Bad Account File is resident on POST	Optionally use this parameter to load the Bad Accounts file onto the POS Terminal. To load the file onto the POS Terminal for the first time, you must either perform a Cold Start or run a general batch file which will insert all bad account records. Maintenance is sent to the POS Terminal any time a change is made to the bad accounts file in the Back Office via Bad Account Maintenance. Any changes made to Bad Accounts through General Batches, generates maintenance to POS Terminals. While in offline mode, bad accounts are validated against the Bad Accounts File which is resident on the POS Terminal. Notes Loading a large Bad Accounts File onto the POS Terminal takes up memory and can affect performance. If your store works with the parameter 'System integrity in system', add the ACCT.QDX file to the QDX Files Checksum Table in Field Engineer's Utilities.
Euro Rate	This parameter defines the conversion rate (numeric value) between the Euro and local currency.
Key-in Fly Buys number without check digit	Fly Buys card numbers may be entered as thirteen or sixteen digit numbers with or without the check digit. Note: Fly-Buy is a card that enables the customer to accrue flying mileage with each purchase. Mileage is earned based on the purchase amount.
'Payment amount' prompt defaults to 'balance due' amount	Check this to assume the payment amount is equal to the balance due amount when tendering.


General POST Parameters 4



Parameter	Description
Maximum items in express orders	Enter the maximum number of items for the system to recognize a sale as an express order.
Check for second ID number in bad account	Select this parameter if you want the system to prompt cashiers to enter a second ID number when customers pay by check.
Allow manual weight	Select this parameter to allow the manual key entry of weight for scaleable items.
Verify weight changes at last keystroke	This parameter will verify the weight from the scale on a manual price weighted item on the last keystroke of the transaction. This eliminates the possibility the weight on the scale could change between the time the department and price is requested and the time the cashier hits the Enter key after price entry. The default setting is unchecked.

Parameter	Description
Do Not Print Expiration Date on Receipt	This parameter provides the option of not printing the card's expiration date on the customer receipt. The default setting is unchecked.
Prompt for Member Secondary ID at the Pin Pad	If this flag is checked, the system will support the entering of a secondary customer ID number on the payment terminal pin pad.
Force Supervisor ID barcode when supervisor intervention is required	This parameter will require the supervisor to scan a barcode when supervisor intervention is required (i.e. overriding control checks), and prevent manual entry of the user ID.
Note: The EAN 13 format for Cashier Bar Codes is 8888 – xxxx – yyyy – c (where xxxx represent the store number, yyyy represents the Cashier ID and c represents the check digit).	
Mask User ID and Password when supervisor intervention is required	This parameter will mask the ID and password on the supervisor prompt, and will mask the cashier electronic journal and the receipt.
PinPad Customer Display	This parameter will direct WinPOS to send all the receipt information to the PinPad, the same way it is sent to the Customer Display: every time an item/department/coupon is scanned, rung or key-entered.
Display Captured Signature on Cashier Display with Accept or Reject	When checked, the captured signature from the EFT terminal will be displayed on the cashier's screen. The cashier will either accept or reject the signature. When unchecked, the captured signature will not display.
Prompt for Frequent Shopper on U-Scan	Select this parameter to prompt for Frequent Shopper Number on the U-Scan Terminal.

Sign On/Off, Secure



This screen contains parameters for controlling sign on, sign off and secure mode operations at POS terminals.

Parameter	Description
Password Required at Sign On	If this parameter is checked, the cashier must enter a password when signing on to POS terminal. If blank, password is not prompted for when signing on to POS terminal.
Change password allowed at sign-on	Check to allow cashiers to change their password at sign-on.
Automatic Open Drawer at Sign on	Check this parameter to have the cash drawer open automatically with each sign-on.

Parameter	Description
Report Required at Sign Off	Select the type of report to be printed at sign off. The possibilities are: • No report: No report printed. • X-read on Receipt: X-read prints on receipt and audit tape. • Name & No. on Receipt: Only the cashier's name and number print on receipt and audit tape. • X-read on Audit: X-read prints on audit tape. • Name & No. on Audit: Only the cashier's name and number print on audit tape.
Change Password Allowed at Sign Off	Check this parameter if the cashier's password can be changed at sign off. For further explanations, refer to the WinPOS User Guide.
Automatic Open Drawer at Sign-off	Check this parameter if you require the cash drawer to open automatically with each sign-off.
Delay (in seconds) for Open Drawer Alarm after Sign-Off	Specify the number of seconds after sign off, to sound the drawer-open alarm.
Password required at sign-off	If this parameter is checked, the cashier must enter a password when signing off the POS terminal.
Number of Minutes Before Automatic Secure Mode	A register automatically enters secure mode or signs off (see next parameter) after a predefined number of minutes without operator use. Enter the number of minutes. 00 means that this function is not in use. POS must be manually put into secure mode by the cashier.
Automatic Secure Mode/Automatic Sign Off	Select Sign Off or Secure to determine whether register automatically signs off or switches to secure mode, after the minutes specified in the 'Number of Minutes Before Automatic Secure Mode' parameter.

Parameter	Description
Omit Confirmation Manual Secure Mode	This parameter provides the option whether the POS will enter secure mode immediately after the secure mode key is pressed, without displaying the prompt to acknowledge. The default is "No" (unchecked).

WIC Options

WIC Options:

1. WIC prompt options.....	Prompt for Exp. Date	[↓]
2. WIC print options.....	Print Exp. Date	[↓]
3. CC for exceeding WIC check amount.....		0
4. CC for exceeding WIC expiry date.....		0
5. CC for bypassing WIC check amount.....		0
6. CC for bypassing WIC expiry date.....		0
7. WIC date.....	Issue Date	[↓]
8. WIC validity period <in days>.....		31

EBT WIC Options:

1. EBT WIC in System.....	[1]
2. Display Eligible Benefits Only.....	[1]
3. EBT WIC Tender Number.....	0
4. CC for Allowing Mixed Basket.....	0

[F2] Update

This screen contains parameters controlling options in support of the WIC (Women, infants, children) program. Some states now support Smart Card WIC EBT using cards with embedded “smart-chips” (which are configured under the EBT WIC Options section). The EFT Pin Pad reads benefit information from the card and updates (writes) data to the card as to which WIC items have purchased. If an EBT WIC card is on a state “hot list” (i.e. card lost, stolen, counterfeited, etc.), the card can be locked by the Pin Pad device. Mixed-basket transactions (that include Electronic WIC and non-Electronic WIC items) are also supported.

Note:

The “Enable WIC Sale” flag in Electronic WIC Item Maintenance determines eligibility for Electronic WIC tendering.

Parameter	Description
WIC Prompt Options	This field determines whether the system prompts for WIC check amount and expiration date. Select one of the following: • No extra prompt • Prompt for Amount • Prompt for Expiration Date • Prompt for Amount and Expiration Date Note If you select prompts for expiry dates and then select 'WIC issue date' below, the POS terminal prompts for issue date.
WIC Print Options	This field determines whether the system prints the WIC check amount and expiration date on the receipt. Select one of the following: • No extra print • Print Amount • Print Expiration Date • Print Amount and Expiration Date Note If you select print options for expiry dates and then select 'WIC issue date' below, the POS terminal prints issue date.
CC for Exceeding WIC Check Amount	Specify the control check to be triggered if the WIC voucher amount is equal to the actual subtotal amount of the transaction.
CC for Exceeding WIC Expiry Date	Specify the control check to be triggered if the WIC voucher date has expired.
CC for Bypassing WIC Check Amount	Specify the control check to be triggered if no amount is entered.
CC for Bypassing WIC Expiry Date	Specify the control check to be triggered if no date is entered.
WIC Date	Select if you want the system to check WIC issue date, expiration date or both issue and expiration date.

Parameter	Description
WIC Validity Period (in Days)	Use this parameter together with the WIC Issue Date, above. Enter the number of days for which the WIC check is valid, taken from the check's date of issue. If the validity period is exceeded, the POS terminal triggers the control check for exceeding WIC expiry date.
EBT WIC in System	When this parameter is set to checked, Smart Card WIC EBT functionality will be enabled in the system. This is used in conjunction with HASP programming.
Display Eligible Benefits Only	When this parameter is checked and EBT WIC in System is checked, only items with redeemable benefit units will be displayed on the receipt.
EBT WIC Tender Number	When EBT WIC in System is checked and this parameter is set to a valid tender number, the selected tender will be used as the EBT WIC tender. Note: A preset tender key needs to be setup on the keyboard and linked to the "EBT WIC Tender Number" as defined here. When the EBT WIC tender key is pressed at the POS, EBT WIC logic is initiated. (The EBT WIC tender key should be pressed in tender mode only.)
CC for Allowing Mixed Basket	Specify the control check to be triggered when an EBT WIC tender is selected to tender a mixed basket (a.k.a. a transaction that includes WIC and non-WIC items). After the EBT WIC Card is accepted, a non-WIC total will print on a receipt (i.e. Mixed Basket Report) and the specified control check will display to restrict updating the benefits on the EBT WIC card until an additional tender has been verified.

Tax, Food Stamp Options

Tax Options:

1. Number of rates to accumulate amounts..... **3**
2. Tax rates to be set ON for the Tax Reversal:
 - 1.☐ 2.☐ 3.☐ 4.☐ 5.☐ 6.☐ 7.☐ 8.☐
3. Total ☐ or individual☐ tax on receipt..... ☐
4. Allow cashier to select specific tax for tax exempt.... ☐
5. Allow cashier to select specific tax for tax reversal... ☐
6. Don't print tax report if tax is zero..... ☐

Food Stamp Options:

1. Any F/S eligible items paid with F/S is tax forgiven.... ☐
2. Any F/S tender forgive tax on all F/S Elig. items (NJ).. ☐
3. Allow non whole-Dollar food stamps..... ☐
4. Food stamp tender number..... **4**
5. Print F/S subtotal on receipt if F/S tendered..... ☐
6. Limit F/S eligible to Bal. Due..... ☐
7. Forgive tax on vendor coupons if F/S tendered..... ☐
8. Forgive tax on F/S partial tenders by highest tax rate.. ☐

[F2] Update

This screen contains parameters concerning taxes and food stamps.


Parameter	Description
Number of Rates to Accumulate Amounts	Specify the number of tax rates to accumulate taxable amounts. If 0, no tax rates are accumulated, except for tax rate 1. If 8, all taxes with a tax rate are accumulated. If 1 through 7, then the first 1 through 7 rates are used to accumulate taxable amounts.
Tax Rates to be set ON for the Tax Reversal	Check which tax rates (1 to 8) are to be set "ON", when the <Tax Reversal> key is used.
Total or Individual Tax on Receipt	If this parameter is checked, each item's tax is detailed on the receipt. If blank, only total tax amount prints on receipt.
Allow Cashier to select Specific Tax for Tax Exempt	If this parameter is checked, the terminal allows the cashier to enter an item's (specific) tax when using the Tax Exempt option.

Parameter	Description
Allow Cashier to select Specific Tax for Tax Reversal	If this parameter is checked, the terminal allows the cashier to enter an item's (specific) tax when using the Tax Reversal option.
Don't print tax report if tax is zero	If this parameter is checked, the tax report for the tax rate is not printed if the tax collected is zero.
Any F/S Eligible Items Paid With F/S is Tax Forgiven	Check this parameter if no tax should be charged for a food stamp eligible item that was paid for with food stamps.
Any F/S Tender Forgive Tax on All F/S Elig. Items (NJ)	Check this parameter if no tax should be charged for food stamp eligible items, when any part of a transaction is tendered with food stamps. The 'Any F/S Eligible Items Paid With F/S is Tax Forgiven' parameter must be checked for this option to be used.
Allow Non Whole Dollar Food Stamps	Check this parameter if food stamps may be tendered in non-whole amounts (e.g. 4.99).
Food Stamp Tender Number	Enter the number of the tender type defined for food stamps. See 'Tender Types' in the 'File Maintenance' chapter.
Print F/S Subtotal on Receipt if F/S tendered	Check this parameter if the subtotal of Food Stamp items should be printed on the receipt.
Limit F/S eligible to Bal. Due	Check this parameter to limit the food stamp balance due amount to the Food Stamp eligible amount.
Forgive Tax on Vendor Coupons if F/S Tendered	Check this parameter to exempt tax on vendor coupons if Food Stamps tendered.
Forgive Tax on F/S Partial Tenders by Highest Tax Rate	When this flag is checked, the system will conform to Illinois rules, forgiving tax on partial tendered food stamp transactions will be performed on the item with the highest tax rate. (See example below).

Example:

Item 100 and Item 200 both sell for \$10.00 and are food-stampable. Item 100 has a combined tax rate of 10%. Item 200 has a combined tax rate of 8%. If this new parameter is set and the transaction is partially tendered with \$10.00 of food stamps, tax will be forgiven on \$1.00 (10% of \$10.00) of the \$20.00 total.

Frequent Shopper Options



This screen contains parameters for controlling frequent shopper options.

Parameter	Description
Freq. Shop. Feature in Use	Check this parameter to enable the frequent shopper feature. If checked, the cashier will be prompted to enter a frequent shopper number at the beginning of the transaction (or press <Enter> to be able to continue with the transaction). For further explanations, see the WinPOS User Guide.

Parameter	Description
Enhanced frequent shopper feature in use	Check this to enable the enhanced frequent shopper feature in the system. The two enhancements are: • Swiping Frequent Shopper card during a ticket. • Frequent Shopper item limit Notes The parameters 'Frequent Shopper feature in use' and 'Enhanced frequent shopper feature in system' may not both be checked at the same time. The Enhanced Frequent Shopper feature in system may not be set if your software key (plug protection) does not allow for it.
Freq. Shop. Range, From:	Specify the beginning number of the range of frequent shopper numbers allowed at the POS terminal. The frequent shopper number can be up to 13 digits.
Freq. Shop. Range, To:	Specify the end number of the range of frequent shopper numbers allowed at the register. The frequent shopper number can be up to 13 digits.
Use Freq. Shop. No. for Check Tender Account Number	Depending on this parameter, the system will or will not prompt to use Frequent Shopper number for the account number of a frequent shopper, during check tendering. If the parameter is checked: If a frequent shopper number is entered at the start of a transaction, the POS terminal does not prompt for an account number during check tendering. The frequent shopper number entered at the start of the sale is used as the account number. If parameter not checked: The POS terminal always prompts for an account number when tendering by check.

Parameter	Description
Freq. Shop. Merchandising Feature	This field determines what type of information is printed on the customer receipt: • None: No frequent shopper information prints on the receipt. • Character: The character specified in Frequent Shopper Print Character is used. • Text Line: The text specified in Frequent shopper receipt print line is used. • Text Line & Savings: Both the character and the text are used.
Freq. Shop. Minimum Purchase Amount	Minimum purchase required before frequent shopper benefits can be given. Zero means that no minimum purchase is required.
Control Check for not Meeting Minimum Purchase for F/S	Specify the control check number to be executed if the frequent shopper minimum amount is greater than the transaction total amount, which means that the customer is not eligible for frequent shopper discounts.
Control Check to Bypass Frequent Shopper	Specify the control check to trigger if the cashier tries to avoid entering of Frequent Shopper number. Like other control checks, this can be set to warning only, inhibit, or call for SVR or MGR keylock.

Parameter	Description
Frequent Shopper discount to be applied to per item price (MSU)	Check this so that Frequent Shopper Discount is applied per item and not to the MSU package price. Example: - MSU (Multiple Selling Unit) Two at the price of \$10. One item will cost \$5. If parameter is not checked, Frequent Shopper discount amount applies to the MSU package price. - MSU - Buy two items for \$10 Frequent Shopper discount is \$2. MSU will be two items for \$8. One item will cost \$4. If parameter is checked Frequent Shopper discount amount applies to the item price. - MSU - Buy two items for \$10 Frequent Shopper discount (\$2) is deducted from the PLU item price (\$5) and not the MSU price. So MSU will be two items for \$6. One item will cost \$3.
Use Frequent Shopper number as member card number	If the parameter is checked, and a Frequent Shopper card is swiped/scanned or entered, the POS Terminal recognizes the card as being a Member card and Frequent Shopper at the same time. The cashier only needs to swipe a card once during a sale. Note The number has to be set up in Card Range Maintenance as a Member Card. If the parameter is not checked, the POS Terminal recognizes the ticket as a Frequent Shopper sale only.
Do not prompt for Frequent Shopper at the beginning of a ticket	This works for enhanced frequent shopper only and prevents the frequent shopper prompt appearing at the beginning of a ticket.

Parameter	Description
Apply Frequent Shopper discount also with any manual price entries	If the parameter is checked, Frequent Shopper discounts apply to manual price entries.
Print Frequent Shopper discount total only (no details)	If the parameter is checked, only the total of frequent shopper discounts will print on the receipt. If unchecked, each item's discount amount will print..
Frequent Shopper receipt template same as member promotion	Select this checkbox if you want the Frequent Shopper receipt printed with the original item price, followed by the item's reduction amount (shown as a negative value).
Frequent Shopper discounts do not reduce net sales	Select this option so that the reports listed below will not net the department totals by frequent shopper discount: • Department Report • Expanded Department Reports • Control Report A new line "Non-Netted Frequent Shopper" has been added to the first two Reports above. In the Expanded Department Reports, a new column has been added "Non-Netted Frequent Shopper".
Member Card qualifies for Frequent Shopper prices	Select this option if Member Card holders are entitled to frequent shopper price discounts.
Use Freq. Shop. Dummy card	Select this option to allow the use of a dummy card to apply frequent shopper discounts (in the case when the customer does not have their card available).
Automatic insert in all tickets	Select this option to have the dummy card number automatically inserted into all tickets missing a frequent shopper number.
Frequent Shopper dummy card number	Enter the Frequent Shopper dummy card number to use.

Discount, Account Options

PCM Discount, Account Options

Discount options:

- 1. Minimum purchase amount for transaction discounts..... 100
- 2. Control Check for not meeting minimum purchase for disc. 0

Account file options:


- 1. Number of digits for Charge Posting account numbers..... 5
- 2. Check tender daily limits on account, amount..... 20.00
- 3. Check tender daily limits on account, count..... 2

[F2] Update

The parameters on this screen are used for controlling discount and in-house charges at POS terminals.

Parameter	Description
Minimum purchase amount for transaction discounts	Minimum purchase amount required for a transaction total based discount.
Control Check for not meeting minimum purchase for disc	Specify the control check to be triggered, if the purchase amount for the discount is below the required minimum.
Number of digits for Charge Posting account numbers	This parameter enables the specifying of the maximum number of digits defined for an Account Number. Upon validation any different number of digits will prompt an error message.
Check tender daily limits on account, amount	This parameter provides the option of specifying the maximum amount allowed for a customer to charge per day.
Check tender daily limits on account, count	This parameter provides the option of specifying the maximum number of charges allowed for a customer per day.

Control Check Options 1




The parameters on this screen are used to set control checks for various POS functions.

Parameter	Description
Bypass Control Check if Conditions Met	Check this parameter if you want the system to bypass existing control checks which require a physical key to be in a specific keylock position, if the key is already in the proper position. If blank, the control check is executed regardless of the key position.
CC for Printer Paper Low	Control checks to be triggered when receipt and audit paper is low.
CC for Keying Weighed Items (no scale)	Control check to be triggered after entering weight.
CC for Exceeding Cancel/Subtract Limit	Control check to be triggered when cancels and subtracts exceed limit amount specified in the following parameter. The message appears when tendering begins.
Cancel/Subtract Limit Amount	Limit amount for cancels and subtracts.

Parameter	Description
CC for Transaction Void	Control check to be triggered when the <Void> key is pressed.
CC for Subtract Next During Item Registration	Control check to be triggered when <Subtract> key is pressed during a transaction.
CC for Item Cancel During Item Registration	Control check to be triggered when the <Cancel> key is pressed for an item, during a transaction. The check is displayed before the item is canceled.
	Note:
	This Control Check is also issued when the Subtract Item button (Keyboard Function #902) is pressed twice in succession and the POS performs the Cancel Item function (voiding the last item added to the ticket).
CC for Subtract Next/Item Cancel After Completion	Control check to be triggered after an item has been canceled, either via the <Cancel> or <Subtract> key. This control check works only as a warning.
CC for Pressing Item Cancel During Template/Slip Print	Control check to be triggered when POS prompts to 'insert slip or check' and the user bypasses the prompt by pressing <Item Cancel>.
CC for Return Transactions, After Completion	Control check to be triggered at the end of a return transaction. This check works only as a warning.
CC for No Sale Within a Transaction	Control check to be triggered for no- sale during a transaction.
CC for No Sale Outside a Transaction	Control check to be triggered for no- sale between transactions.
CC for a Credit Card Tender that Exceeds Eligible Amt	Control check to be triggered when credit card amount exceeds limit amount.
CC for Saving Transactions with Partial Tender	Control check to be triggered when a transaction is saved with partial tendering.
CC for Price Override	Control check to be triggered when the price <Override> key is pressed.
CC for Bypass Check Printing	Control check to be triggered when an attempt is made to avoid check printing.

Parameter	Description
CC for Bypass Check Endorsement	Control check to be triggered if the cashier does not insert the check for endorsement.
CC for Bypass Tender Template Printing	Control check to be triggered if the cashier does not insert the check for check-front printing.

Control Check Options 2



Parameter	Description
CC for Off-line Bad Account Request	Control check to be triggered if the POS terminal is off-line, and a bad account check should be done. The bad account file cannot be checked, but a supervisor or manager manually authorize the transaction.
CC for Off-line Supervisor Request	Control check to be triggered if the POS terminal is off-line, and a supervisor is required to authorize some kind of transaction.

Parameter	Description
CC for Off-line ECCA Request	Control check to be triggered if the POS terminal is off-line, and an ECCA check is made.
CC for Save/Recall ticket in off-line mode	Check this to enable Save/Recall activities at the POS Terminal in offline mode. Each ticket saved in offline mode is stored in the directory: C:\PCMPOS\QDX with the file name: PXXYYYYY.SAV where XXX represents the POS number and YYYY represents the ticket number. Transactions saved in offline mode can only be recalled from the POS Terminal they were saved on. The ticket shows the POS Terminal number from where the Recall must be done. Note The End of Day process deletes *.SAV files from the POS Terminal. This means that tickets can be recalled only for the current day. During offline mode you can only recall tickets that were saved in offline mode. Save/Recall in offline mode can be performed by using the Customer's ID.
CC for Customer Account off-line	Enter the Control Check number to trigger when the POS Terminal is off-line.
CC for Customer Account not on file	Enter the Control Check number to trigger when the Customer Account number entered does not exist on the file.
CC for Customer Account insufficient funds	Enter the Control Check number to trigger when the Customer does not have enough credit to cover the purchase.
CC to restrict redemption of Customer Accounts out of sale	Not in use.

Parameter	Description
CC for exceeding qty limit at scanning	Enter the Control Check number to trigger when the scanning quantity limit has been exceeded.
Scanning qty limit	The quantity limit for scanning or manually keying in items.
CC for exceeding max. amount in negative transactions	Enter the Control Check number to trigger when the ticket amount exceeds the <i>maximum amount allowed for negative transactions</i>. The POS Terminal checks if the amount has been exceeded only when the <i>Total</i> key is pressed.
Maximum amount for negative transactions	Enter the maximum amount allowed for negative transactions to be performed on the POS Terminal. Once the value has been exceeded, the Control Check is triggered.
CC to bypass 'cashier not found' during offline sign-on	If you enable the parameter 'Cashier File is resident on POST', you can use this Control Check to bypass the message 'Cashier not found' when signing on in offline mode.

Var. Price/Weight Item Codes 1

Variable Price/Weight options p.1:

Starting Digits	02	04	99
Code in use	☒	☐	☒
PCDU required	☐	☐	☐
Digits in price	4	0	4
Decimal places	2	0	2
Price ☐ or Weight ☒	☐	☐	☒

[F2] Update

The first two digits of the PLU item number may be used to represent an item price or a weight. For example, items whose numbers begin with the digits 02 weigh 1 pound; items whose numbers begin with 04 are sold for \$.99. This is called a 'variable price/weight' code. The price/weight codes are fixed by the system, and they can be used as required.

The codes are 02, 04, 99, 20 through 29. In order to use any of these price/weight codes for PLU items, a number of parameters have to be defined. Parameters for the codes 02, 04, and 99 are defined via the Variable Price/Weight Item Codes 1 option. Parameters for the codes 20 to 29 are defined via the Variable Price/Weight Item Codes 2 option.

The Variable Price/Weight Item Codes 1 parameter screen displays the starting digits (price/weight codes) 02, 04 and 99.

Note:

With UPC2, zero-priced items are allowed.

Set the following parameters for each of the codes to be used.

Parameter	Description
Code in Use	This code is used, meaning that a variable weight or price is encoded in the PLU number.
PCDV Req'd.	Check this parameter if price check digit verification is required.
Digits in Price	Greatest number of digits in UPC price or weight field.
Decimal Places	Number of decimal places for price or weight field in UPC.
Price or Weight	Check this field if the code denotes a variable weight. Leave blank, if the code denotes a price.

Var. Price/Weight Item Codes 2

Starting Digits	20	21	22	23	24	25	26	27	28	29
Code in use	☒	☐	☐	☐	☐	☐	☐	☐	☐	☐
PCDU required	☐	☐	☐	☐	☐	☐	☐	☐	☐	☐
Digits in price	4	4	5	4	0	4	0	0	0	0
Decimal places	2	2	2	2	0	2	0	0	0	0
Price [] or Weight [x]	☐	☐	☐	☐	☐	☐	☐	☐	☐	☐

[F2] Update

This screen displays the starting digits 20 to 29 (price/weight codes). Set the parameters for the codes to be used. For instructions, refer to 'Variable Price/Weight Options 1', above.

Restricted Sale Birthday Validation

ISS PCM

Restricted Sale Birthday Valid.

Restricted Sale/Birthday options p.1:

1. Restricted Sale/Birthday feature in use..... [F]
2. Allow delayed age verification..... [F]
3. Cashier age verification in use..... [F]
4. Prompt to accept birthday..... [F]
5. CC for bypassing birthday prompt..... 0
6. Birthday validation print option..... Both [F]

department layouts:

	1	2	3	4	5	Both
Department Number	21	0	0	0	0	
Set No (1-3)	1	0	0	0	0	
CC Restricted sale:						
for customer	0	0	0	0	0	
for cashier	0	0	0	0	0	
Age required:						
for customer	21	0	0	0	0	
for cashier	21	0	0	0	0	
CC Birthday val.	0	0	0	0	0	

[F2] Update

The Restricted Sale/Birthday Validation feature allows you to implement department-based validation on restricted items such as liquor and cigarettes. This feature can be set up in one of three ways:

- The sale of an item can be restricted at a certain time of the day (restricted sale).
- The sale of an item can be restricted to individuals who have reached a certain age (birthday validation).
- The sale of an item can be restricted both by the time of day and the age of the customer (restricted sale and birthday validation).

You can set restrictions for up to ten departments. All items in the restricted departments are subject to validation. Validation occurs both upon department and item code entry, at a POS terminal.

In the upper part of the screen, set the following parameters.

Parameter	Description
Restricted Sale/Birthday Feature in Use	Check this parameter, if the Restricted Sale/Birthday feature is being used. A restricted sale means the item can only be purchased at a particular time of day (e.g., beer, wine). A birthday validation means the item can only be purchased by an individual of a particular age.
Allow delayed age verification	Check this parameter to delay age verification for the restricted item(s) until the entire transaction is totaled.
Cashier age verification in use	Check this parameter to verify the cashier's age before permitting the restricted item to be sold.
Prompt to Accept Birthday	Check this parameter if you want the POST to ask the cashier for birthday verification. If the birth date was retrieved through Biometric Identification, this parameter will be ignored and the cashier will not be prompted to accept the birth date.
CC for Bypassing Birthday Prompt	The control check to be executed if the cashier does not enter a birth date for birthday validation.
Birthday Validation Print Option	This field determines whether the birth date is printed on the receipt or audit tape or both. Select the required option.

In the lower part of the screen, you can set restrictions for 5 departments. Each of the columns refers to a department. Enter the following information for each department.

Parameter	Description
Department Number	Enter the number of the department to be restricted. Whenever this restricted department is rung up on the register, the validation process is executed.

Parameter	Description
Set No.	Enter the layout number (1, 2 or 3). This number refers to the layouts defined via the Restricted Sales Times option (see relevant section, later in this chapter). This number determines the selling times allowed for this restricted department. If this field is set to zero, then the restricted sale time option is not used for this particular department.
CC Restricted Sale	If you entered a layout number in the previous field, you can set up a control check (for both the customer and cashier separately) on this department. This control check triggers if an item is being purchased at an invalid time of day. If you enter 0 for a control check, no check is executed and all customers are allowed to buy items (and cashiers are allowed to sell) regardless of the time of day.
Age Required for customer, cashier	Enter the minimum age required (1-99), for a customer to purchase and a cashier to sell restricted items in this department (each separately). Enter 0 to disable the birthday validation option for this department.
CC Birthday Val	If you entered an age in the previous field, you can set up a control check on this department. This control check triggers if the customer (or cashier) has not yet reached the age to purchase (or sell) items in this department. If you enter 0 for a control check, no check is executed and all customers are allowed to buy (and all cashiers allowed to sell) items regardless of their age.

Restricted Sale Layouts

PCM Restricted Sale Layouts

Restricted Sale/Birthday options p.2:

Restricted Sale/Birthday department layouts:

	6	7	8	9	10
Department Number	13	0	0	0	0
Set No (1-3)	1	0	0	0	0
CC Restricted sale:					
for customer	0	0	0	0	0
for cashier	0	0	0	0	0
Age required:					
for customer	21	0	0	0	0
for cashier	21	0	0	0	0
CC Birthday val.	0	0	0	0	0

[F2] Update

This screen allows you to set restrictions for five additional departments. For instructions, see 'Restricted Sale Birthday Validation', above.

Restricted Sale Times

	Start-1	Stop-1	Start-2	Stop-2
Monday - Thursday	07:00	12:00	00:00	00:00
Friday	07:00	12:00	00:00	00:00
Saturday	03:00	04:00	00:00	00:00
Sunday	02:53	03:00	00:00	00:00

Set Valid Days:

Mon	Tue	Wed	Thu	Fri	Sat	Sun
[X]	[X]	[X]	[X]	[X]	[X]	[X]

[F2] Update [F6] Next Page

This screen allows you to define up to three sets of selling times for restricted departments. The relevant time layout number (1, 2 or 3) for a department is entered via the Restricted Sale Birthday Validation and Restricted Sale Layouts screens.

You can set up two sets of 'start' and 'stop' selling times for different days of the week. In each set you can specify selling times, separately for weekdays (Monday to Thursday), Fridays, Saturdays and Sundays. For each of these, enter the start and stop time. Enter the times in a 24-hour format (i.e., noon = 1200 and midnight = 0000). If needed, enter a second 'start' and 'stop' time.

After setting selling times, press *F2* to record the definitions. Press *F6* for more sale time sets.

Restricted Sale Special Dates

This option allows you to override sales restrictions for specific dates (and times).

Once you specify dates and times you can link to previously-defined layouts (using the Link No. columns). Use the F8 (List) to link to the desired layouts (1 through 10). These layouts contain specific rules, for example, which departments or items are restricted.

No.	Date	Start-1	Stop-1	Start-2	Stop-2	Link No.
1	06/30/2002	02:53	03:00	00:00	00:00	YNNNNNNNNN
2	10/13/2001	03:00	04:00	00:00	00:00	NNNNNNNNNN
3	00/00/00	00:00	00:00	00:00	00:00	NNNNNNNNNN
4	00/00/00	00:00	00:00	00:00	00:00	NNNNNNNNNN
5	00/00/00	00:00	00:00	00:00	00:00	NNNNNNNNNN
6	00/00/00	00:00	00:00	00:00	00:00	NNNNNNNNNN
7	00/00/00	00:00	00:00	00:00	00:00	NNNNNNNNNN
8	00/00/00	00:00	00:00	00:00	00:00	NNNNNNNNNN
9	00/00/00	00:00	00:00	00:00	00:00	NNNNNNNNNN
10	00/00/00	00:00	00:00	00:00	00:00	NNNNNNNNNN

[F2] Update [F8] List

Tare Weight Parameters (1-30)

This option serves to define tare weights for weighed items. Tare weight is the weight of a container that is deducted from the gross weight of the item to obtain the net weight.

For a tare weight to be deducted from a weighed item, the following must be performed in the item record:

- The Weighed Item parameter must be checked.
- The tare code representing the weight of the container must be entered in the Tare Weight field.

For example, if an item is sold by weight, and its container weighs .25 pounds, then a tare weight needs to be set up at 0.25. In the

PLU record, specify that this item is weighed. Then enter the tare code representing 0.25 in the Tare Weight field. This automatically subtracts 0.25 from the item weight entered at the POS terminals.

Tare codes can be defined in terms of weight or percentages. Tare codes 1-30 are allocated for tare weights. Tare codes 31-60 are allocated for tare percentages.

To define tare weights, select Tare Weight Parameters (1-30) from the POST Parameter File 1 menu. The Tare Weight Parameters (1-30) screen displays.

No.	Description	Weight
1		.010
2		.020
3		.030
4		.040
5		.050
6		.060
7		.070
8		.080
9		.090
10		.100

[F2] Update [F3] Cancel

07/15/2003 10:38:06 Copyright Fujitsu-ICL Inc.

- **To enter a new tare weight or update an existing one**
- 1 Move the cursor to the required code, using the *Enter*, *Tab* or *Down Arrow* keys.
 - 2 Type or overwrite the weight, up to four digits. Do not type in the decimal point. For example, for 1 pound, type 1000. This displays as 1.000. If the unit of measurement used for weight is pounds, the tare weight displays on the POS terminal with two digits after the decimal point. If the unit is kilograms, it displays with three digits after the point.
 - 3 Press *F2* to update the definition.

% Tare Weight Parameters (31-60)

This option serves to define tare weight percentages for weighed items. It works in the same way as described above, however, the tare weight subtracted from an item must be defined here as a percentage of the item weight.

To define tare weight percentages, select % Tare Weight Parameters (31-60), from the POST Parameter File 1 menu. The % Tare Weights Parameters screen displays.

No.	Description	Weight
31	TARE WEIGHT	.010%
32	TARE WEIGHT	.020%
33		.000%
34		.000%
35		.000%
36		.000%
37		.000%
38		.000%
39		.000%
40		.000%

[F2] Update [F3] Cancel

07/15/2003 11:35:26 Copyright Fujitsu-ICL Inc.

- To enter a new tare weight percentage or update an existing one
 - 1 Move the cursor to the required code, using the *Enter*, *Tab* or *Down Arrow* keys.
 - 2 Type or overwrite the percentage, up to four digits.
 - 3 Press *F2* to update the definition.

Signs



This screen contains parameters for setting the various signs to be printed at POS terminals.

Parameter	Description
Currency	The currency sign to be used.
Minus	The minus sign to be used.
Decimal	The sign to be used for decimal quantity input (usually a point).
Format	The format sign to be used.
Non Taxable Print Character	The sign to print on receipt and audit tape for non taxable items (usually space).
Multiple Tax Print Character	The sign to print on receipt and audit tape when two or more taxes are applicable.

Parameter	Description
Food Stamp Print Character	The character to be printed next to a food stamp eligible item.
Non Food Stamp Print Character	The character to be printed when a sale is not a food stamp.
Cost Plus Print Character	The character to be printed next to a Cost Plus item or department.

Parameter	Description
Non Cost Plus Print Character	The character to be printed when a sale is not a Cost Plus item or department.
Frequent Shopper Print Character	The character to be printed next to an item that has a Frequent Shopper discount.
Non Frequent Shopper Print Character	The character to be printed when a sale does not have a Frequent Shopper discount.
Print currency on check (Dollar)	For Check printing, enter the text to print on the check. For example, 'Dollars'.
Print currency on check (Cents)	For Check printing enter the text to print on the check. For example, 'Cents'.

WIC CVV Options

PCM

WIC CVV Options

WIC CVV Options:

1. WIC CVV prompt options.....No extra prompt [↑↓]
2. WIC CVV print options..... No extra print [↑↓]
3. CC for exceeding WIC CVV check amount..... 0
4. CC for exceeding WIC CVV expiry date..... 0
5. CC for bypassing WIC CVV check amount..... 0
6. CC for bypassing WIC CVV expiry date..... 0
7. WIC CVV date..... Issue Date [↑↓]
8. WIC CVV validity period (in days)..... 0
9. Allow WIC CVV in a Mixed Basket Transaction..... []
10. Allow Split Tendering in a WIC CVV Transaction..... []
11. Maximum number of WIC CVV vouchers in a ticket..... 0
12. Display WIC CVV Eligible Total on Cashier Display..... []
13. Enforce tendering declared vouchers in WIC CVV Sale Mode..... []

[F2] Update

The WIC CVV (Cash Value Vouchers) Options support the USDA initiative to increase its participants' choices by offering fresh and processed fruits and vegetables. While traditional WIC checks are item-based, dollar-based WIC CVV vouchers facilitate the purchase of fruits and vegetables since few fresh fruits and vegetables are sold in standard weight units (with uniform bar codes) and their prices may vary considerably (between seasons, regions and stores).

Parameter	Description
WIC CVV Prompt Options	This field determines whether the system prompts for WIC CVV amount and expiration date. Select one of the following: • No extra prompt • Prompt for Amount • Prompt for Expiration Date • Prompt for Amount and Expiration Date
WIC CVV Print Options	This field determines whether the WIC CVV amount and expiration date prints on the receipt. Select one of the following: • No extra print • Print Amount • Print Expiration Date • Print Amount and Expiration Date
CC for Exceeding WIC CVV Check Amount	Specify the control check to be triggered if the ticket subtotal is greater than the total amount of the declared WIC CVV vouchers.
CC for Exceeding WIC CVV Expiry Date	Specify the control check to be triggered if the WIC CVV date has expired.
CC for Bypassing WIC Check Amount	Specify the control check to be triggered if no WIC CVV amount is entered.
CC for Bypassing WIC CVV Expiry Date	Specify the control check to be triggered if no WIC CVV expiration date is entered.
WIC CVV Date	Select if you want the system to check the WIC CVV issue date, expiration date or both issue and expiration date.

Parameter	Description
WIC CVV Validity Period (in Days)	Use this parameter together with the WIC CVV Date, above. Enter the number of days for which the voucher is valid, taken from the voucher's date of issue. If the validity period is exceeded, the POS terminal triggers the control check for exceeding WIC CVV expiry date.
Allow WIC CVV in a Mixed Basket Transaction	If checked, a WIC CVV voucher may be used as tender outside of a WIC CVV mode sale.
Allow Split Tendering in a WIC CVV Transaction	If checked, a consumer will be allowed to pay for part of a transaction with a WIC CVV voucher, and part with a different tender.
Maximum number of WIC CVV vouchers in a ticket	This parameter defines the maximum number of WIC CVV vouchers that can be tendered in a ticket. The default value is of 0 means "no limit" (or no validation).
Display WIC CVV Eligible Total on Cashier Display	If checked, the total amount of items in the ticket that are eligible to be paid using CVV vouchers will display when the ticket is totaled.
Enforce tendering declared vouchers in WIC CVV Sale Mode	When this parameter is checked, WIC CVV voucher amounts tendered must match the voucher amounts declared in WIC CVV Sale Mode.

Note:


The "WIC CVV Prompt Options" parameter (6-1-2-15 #1) must be set to either "Prompt for Amt." or "Prompt for Amt. & Exp. Date" for WIC CVV voucher amount entry to be prompted for at the beginning of the ticket.

POST Parameters 2

This option provides access to screens where you can enter the retailer information to be printed on multi-part receipts, when tendering with a credit card. POST User hooks, page 1, 2 and 3,

can also be accessed from this menu. See the Custom Links Manual for more information.

To access the Retailer Information option, select POST Parameters 2 in the System Parameters menu. The Post Parameter File 2 menu displays.



Each option on this menu leads to a screen containing a group of parameters. Select the required option to display the parameters screen. Refer to the relevant section below, for parameter descriptions.

Electronic Payment Settings

Electronic Payment settings

- 1. EPS Payment provider..... MTX [↕]
- 2. AUTH file directory on the server.....
- 3. Capture EBT GEN number for manual account entry..... []
- 4. CC for overrideable decline..... 0
- 5. Private Credit Card Tender..... 0
- 6. Pos Timeout For ISS45 Integrated Payments..... 0
- 7. Apply Idle Locking Mode for Pin Pad..... []

[F2] Update

This screen contains parameters for establishing the EPS settings used for electronic payments tendering.

Parameter	Description
EPS Payment Provider	Select the code for your EPS Payment Provider. None, PLD for Ingenico, MTX for Hypercom, KC for Kincaid or EPS for Concord.
AUTH file directory on the server	This field provides the path to the directory where the authorization files (xxx.Auth.dat and xxxSNF.dat files) are stored. The recommended location for these files is C:\PaymentMaster\.
Capture EBT GEN Number for manual account entry	This parameter provides the option to capture EBT GEN Number for manual account entry. This parameter must be set to Yes.
CC for overrideable decline	This parameter provides the option of selecting the Control Check required when overriding a EPS payment decline (e.g., Exceeds Limit).
Private Credit Card Tender	Not Used.

Parameter	Description
POS Timeout for Integrated Payments	Not Used.
Apply Idle-Locking Mode for Pin Pad	If checked, the POS application will instruct the Pin Pad to lock itself at any end of ticket and unlock itself only when a new ticket starts.

Retailer Information 1-3

```

ISS45 PCM
Retailer Information 1 - 3

Retailer information number 1:
Line number 1.....MASTER CARD BUSINESS
Line number 2.....YOUR STORE NAME
Line number 3.....STORENEXT
Line number 4.....ISS45
Line number 5.....TESTING

Retailer information number 2:
Line number 1.....AMERICAN EXPRESS
Line number 2.....YOUR STORE NAME
Line number 3.....
Line number 4.....
Line number 5.....

Retailer information number 3:
Line number 1.....DINERS CLUB
Line number 2.....YOUR STORE NAME
Line number 3.....
Line number 4.....
Line number 5.....

[F21 Update]

```

This screen enables you to enter the details of three credit card retailers. For each retailer, you can enter up to 5 lines of information. These lines are printed on a multi-part receipt below the header, during a transaction with a credit card.

After entering retailer information, you need to link it to the corresponding tender type. This is done via the Retailer Information field in the Tender Types option

Type in the required information in the 5 lines available for each retailer, and press *F2* to record the definition.

Retailer Information 4-5

The screenshot shows a terminal window titled "ISS45 PCM" with a subtitle "Retailer Information 4 - 5". The screen is divided into two sections for entering retailer information. The first section, "Retailer information number 4:", lists five line numbers (1 through 5) with dotted lines for input. The second section, "Retailer information number 5:", also lists five line numbers (1 through 5) with dotted lines for input. At the bottom of the screen, there is a button labeled "[F2] Update".

```
ISS45 PCM
Retailer Information 4 - 5

Retailer information number 4:
Line Number 1.....
Line number 2.....
Line number 3.....
Line number 4.....
Line number 5.....

Retailer information number 5:
Line number 1.....
Line number 2.....
Line number 3.....
Line number 4.....
Line number 5.....


[F2] Update
```

This screen allows you to enter retailer information for two more credit card retailers. For details, refer to Retailer Information 1-3 above..

POST User Hooks

POST user hooks are user-definable applications which can be activated before, or after, certain functions in the POS terminals.

To access this option, select POST User Hooks, page 1, 2 or 3, from the POST Parameter File 2 menu.



The three pages list parameters which are used to activate pre-defined user hooks.

Customer Display Messages

This option is used to customize the messages appearing on the customer display. Different messages can be programmed to display for the POS terminal when in a 'closed' state, as well as in 'next customer' (sales) state.

To access this option, select Customer Display Messages from the Post Parameter File 2 menu. The Customer Display Messages screen appears.

PCM Customer Display Messages

Customer Display Message for "POS CLOSED":

Width <Note:if bigger than customer display width, message will scroll>:50

Line	Text
1	***SORRY THIS LANE IS CLOSED***
2	
3	
4	

Customer Display Message for "NEXT CUSTOMER":

Width <Note:if bigger than customer display width, message will scroll>:30

Line	Text
1	"NEXT CUSTOMER"
2	
3	
4	

IF21 Update

The screen has two main sections. The top section is used for programming the customer display in 'POS CLOSED' state, and the bottom section for 'NEXT CUSTOMER' state.

There are four lines available for messages, however, if you are using a two-line display, only two messages can be displayed.

Messages may consist of any alphanumeric character, and can be in upper or lower case.

➤ **To program the customer display**

- 1 Type in the required width of the message for the 'POS CLOSED' state. (Maximum of 49 characters).

Notes

If the width entered is greater than the customer display width, the message scrolls, or if zero (0), the PPM standard message displays.

- 2 The width entered above must be at least the width of the message you type in, or it does not display correctly.
- 3 Type in the messages for 'POS CLOSED' in lines 1 to 4 as required.
- 4 To enter messages for the 'NEXT CUSTOMER' state, repeat the above procedures.

- 5 To clear a message, just delete it with the *Space Bar* or *Delete* key.
- 6 Press *F2* to update the definition.

Reorganize Receipt

The Reorganize Receipt option is used to give you maximum flexibility over the organization and order of sales information on the customer receipt. You can also print summaries of customer savings.

ISS45 can print EFT receipt data received from MTXEPS for EFT approvals, balance inquiries, card activations (deactivations and recharges) and declines.

If the "Use MTX Receipt Data" parameter is enabled (see below), MTXEPS receipt data will be written to the Electronic Journal file so that it will be displayed as a text transaction.

Note:

MTXEPS WinEPS must be setup to require a receipt for the tender. EFT receipts (including decline receipts) will print only if the tender has the ("Z") TAC setup in WinEPS under Terminal Configuration.

Note:

MTXEPS receipts do not need to be set up by the store and are hard-coded to print in a specific manner. However, additional store information can be added through MTXEPS.

Note:

By default, check account numbers are not masked. The store can modify the tender to be truncated through MTXEPS.

To access this option, select Reorganize Receipt from the POST Parameter File 2 menu. The Reorganize Receipt screen displays.

Reorganize Receipt Parameters Page 1		
1.	Buffer printing.....	[✓]
2.	Combine same items.....	[]
3.	Omit voided and cancelled items.....	[]
4.	Your savings today.....	[✓]
5.	Sort receipt.....	[✓]
6.	Main sort.....	Department name + total [↓]
7.	Second sort.....	Alpha [↓]
8.	Combine same weighed items.....	[✓]
9.	Use MTX Receipt Data.....	[]

[F2] Update

Define the following parameters.

Parameter	Description
Buffer Printing	Check this parameter to store transaction information in the printer buffer (memory), until completion of the transaction. Use this option to enable sorting of the items. When buffered printing is enabled, the printer beeps each time an item is entered. You can, if required, set up the POS terminal back office menu to include the function 'Abort buffer printing'.
Combine Same Items	If you check this parameter, multiples of an item print as one entry on the receipt, regardless of the order in which they are rung up. This option works only if you select Buffer Printing.

Example:

ORANGE JUICE		
3 @	\$2.99	\$8.97
NOODLES		
2 @	\$1.50	\$3.00
STRAWBERRY YOGURT		
5 @	\$1.65	\$8.25

Parameter	Description
Omit Voided and Canceled Items	Check this parameter to avoid printing voided and canceled items. This works only if you select Buffer Printing.
Your Savings Today	If you want to print this text line with the relevant savings description and amount, check this parameter. If items on promotion, reduction or offer have been rung up, the relevant message prints. Example: <u>YOUR SAVINGS TODAY!</u> TTL DISCOUNTS SAVINGS TTL REDUCTIONS SAVINGS TTL PROMOTIONS SAVINGS TTL OFFERS SAVINGS
Sort Receipt	If you want the receipt sorted, (see options below), check this parameter. To sort receipts, you must check the Buffer Printing parameter.
Main Sort	Select one of the sort options from the drop-down list: • None • Department Name • Department Name + Total • Item Name • Price Ascending • Price Descending • Department Number
Second Sort	• None • Alpha • Price Ascending • Price Descending
Combine Same Weighed Items	Check this parameter to combine (same) weighed items on the customer receipt.

Parameter	Description
Use MTX Receipt Data	When this parameter is checked, the system will use MTX receipts on EFT transactions. If this parameter is unchecked, ISS45 Templates will be used for EFT receipt printing. The "Buffered printing" flag (above) must be checked for MTXEPS receipts to work correctly

For examples of receipt layout possibilities, the Chapter 2 in the WinPOS User Guide.

Rounding Parameters

This option is used to define the rules for rounding up, or down, the balance due by the customer. This influences the change amount due to the customer. Rounding is normally, but not necessarily, applied to cash tenders. There is a parameter in Tender Types Maintenance which you must check to enable this function.

Example: If only one cent is due in change, the system can round this down to zero, or if four cents, round up to five.

To access this option, select Rounding Parameters from the POST Parameter File 2 menu. The rounding parameters screen displays.

- **To set up rounding parameters**
- 1 Press *Enter* or *Tab* to move the cursor to the required cent value.
 - 2 Type in the appropriate rounding value for each cent value. For example: For one cent, you may decide to round *down* to zero. In this case enter 0 under 1. To round *up* from 4 cents to 5 cents, enter 5 under the 4.
 - 3 Press *F2* to update the definition.

Member Card and Promotion

This menu contains options for Member Card and Member Promotion.

Member Card

This option leads to the parameters required for Member Cards.

To access this option, select Member Card from the Member Card and Promotion menu in POST Parameter File 2. The Member Card screen displays.

Parameter	Value	Default
1. Redemption end date.....	01/01/2003	
2. Pending redemption start date.....	01/01/1999	
3. Redemption tender.....	CASH	[↑]
4. Redemption option.....	None	[↓]
5. Qualified spend option.....	Print QF for Member Card customers only	[↑]
6. Member Card in system.....		[N]
7. Member Card number includes check digit.....		[]
8. Key-in Member Card number without check digit.....		[N]
9. Allow scanning of Member Card during a transaction.....		[N]
10. Member Card name in system.....	MEMBERSAVERS	
11. Redemption points value : 1 points =	.01 <value>	
12. Display Member name on customer display.....		[N]
13. Display Member name on cashier display.....		[N]
14. Print Member name on receipt.....		[N]
15. Length of secondary ID number <CCMS only>.....	10	
16. Automatically accept combine card as tender.....		[]
17. Display Member Card description on cashier display.....		[N]
18. Display Member Card description on customer display.....		[]
19. Display Member name received from COREMA.....		[N]
20. Print offer progress on receipt even if promotion was not triggered		[N]

[F2] Update

Enter or check the following parameters as appropriate.

Parameter	Description
Redemption End Date	Not used.
Pending Redemption Start Date	Not used.
Redemption Tender	Select from the drop-down list. This is the tender you could choose to pay when redeeming customer points.

Parameter	Description
Redemption Option	When redeeming customer points, you can either redeem ALL points, or a partial amount. Select the appropriate option.
Qualified Spend Option	Select the appropriate option from the drop-down list. • Print QF for Member Card customer's only • Print QF on all receipts • As option 1 + Member Card points • As option 2 + Member Card points • Print only TOTAL POINTS (TFS)
Member Card in system	This parameter provides the option of defining a member card in the system.
Member Card number includes check digit	Specifies that member card numbers include check digit.
Key-in Member Card number without check digit	Allows cashiers to manually enter member card numbers without check digit.
Allow scanning of Member Card during a transaction	Check this parameter to allow cashiers to scan a bar-coded Member Card during a transaction without having to first press the preset Member Card key. To enable this feature you must define the Member Card in Card Range Maintenance, as one of the first five ranges.
Member Card name in system	Define your own Member Card name.
Redemption points value: 10 points = 5.00 (value)	Specify the points redemption (currency) value.
Display Member name on customer display	When checked this parameter will display the customers name as it appears on their member card.
Display Member name on cashier display	When checked this parameter will display the customers name as it appears on their member card.

Parameter	Description
Print Member name on receipt	Check to print member name on receipt.
Length of secondary ID number (CCMS only)	This parameter specifies the maximum number of characters allowed for a secondary ID number – an additional unique ID number required, for example, when a customer misplaces their Member Card.
Display Member card name on customer display	This parameter provides the option to display the name of the Member Card holder on the Customer Display once the card is swiped or scanned.
Display Member card name on cashier display	This parameter provides the option to display the name of the Member Card holder on the Cashier Display, once the card is swiped or scanned.
Print Member name on receipt	This parameter provides the option to print the name of the Member Card holder on the printed receipt.
Length of secondary ID number <CCMS Only>	This parameter specifies the maximum number of characters allowed for a secondary ID number, an additional unique ID number required, for example, when a customer misplaces their Member Card.
Automatically accept combine card as tender	This parameter provides the option of specifying that once a Combined Card was swiped at the beginning of the ticket a message will be displayed at the end of the ticket, asking whether the customer wishes to use this card as Tender.
Display Member card description on customer display	This parameter provides the option to display the name of the Member Card (i.e. MemberSavers) on the Customer Display once the card is swiped or scanned.
Display Member card description on cashier display	This parameter provides the option to display the name of the Member Card (i.e. MemberSavers) on the Cashier Display, once the card is swiped or scanned.

Parameter	Description
Display Member Name from Corema	This parameter specifies that after a PAN (PAN=Personal Account Number) is sent to Corema and data is received for the specified customer, the customer's name will be displayed.
Print Offer Progress on Receipt Even if Promotion Was Not Triggered	If this flag is checked, the system will print the progress of all offers with the "Report to Loyalty Server" flag set and that are valid for that member.

Note:


This feature is only available for Enhanced Promotions.

Press *F2* to update the definition.

Member Promotion

This option leads to the parameters required for Member Promotion.

To access this option, select Member Promotion from the Member Card and Promotion menu in POST Parameter File 2. The Member Promotion screen displays.



Parameter	Description
Enhanced Promotion description	Type in the description for the enhanced promotion.
Total Enhanced Promotion description	Type in the description for the total enhanced promotion.
Total for Member Promotion description	Type in the description for total member promotion.
Member Promotion discounts do not reduce net sales	Check this parameter so that member promotion discounts don't decrease net sales figures.

Additional Tender Information

Not used at this time.

Barcoded Tender Options

This option leads to the parameters required for Barcoded Tenders.

To access this option, select Barcode Tender Options from the Additional Tender Info menu in POST Parameter File 2. The Barcoded Tender Options screen displays.

Barcoded Tender Options	
Barcoded tender Active.....	[1
Barcoded tender number.....	0
Barcoded tender prefix.....	0
Barcoded tender value location.....	0
Barcoded tender value length.....	0
Additional Barcoded Tender:	
Additional Barcoded Tender Prefix.....	0

[F2] Update

This screen contains parameters for handling barcoded tenders (i.e. Coinstar).

Coinstar is a tender type, whereby coins are inserted into a (Coin Star) machine at a store. Once the machine accepts the coins, it produces a barcoded ticket, showing the amount of coins inserted.

The barcodes are made up of 13 digits (XX-YYYYY-ZZZZZ-C). Whereby:

'XX' is the prefix. This can be anywhere between 10 - 99. 'YYYYY' is the number assigned within the coinstar system. 'ZZZZZ' is the value of the tender (\$ZZ.ZZ). 'C' is the Control Check.

Note

Parameters defined in the Back Office determine the first two digits (prefix), the tender number, the value location and value length.

The coinstar barcode is scanned as a tender type, reducing the ticket value. The ticket may be used to overtender a sale allowing cash change.

In case the value of the ticket exceeds \$99.99, the value of 'ZZZZZ' will be '00000' and the cashier is prompted to enter a price manually.

Note

If the barcode is scanned during sale mode, an error message appears.

Coinstar tenders may be voided, canceled and subtracted. The tender correction and manual entry functions may also be used on coinstar tenders.

Additional Barcoded Tenders

ISS45 allows you to implement additional barcoded tenders. This feature allows the store issue redeemable barcoded vouchers to customers that are can be later be used at tendering. (For example, the store may wish to issue the customer a voucher for the amount of a check-cashing fee). When the additional barcoded tender is scanned, the balance due is reduced. If the amount in the barcode is greater than the remaining balance due and the tender set in the barcode allows for over-tendering, change is given as cash

Additional Barcoded Tenders will be accepted only in tender mode or as part of a tender purchase order. The format for the additional barcoded tender is fixed. The only flexible part is the prefix (which is defined in the parameter below).

The format for the additional bar coded tender is AA-TTT-NN-PPPPP-C (defined as follows).

- AA – prefix (Parameter defined)
- TTT – tender number
- NN – number assigned when creating the barcode (can be any number and the POS application will not validate it).

- PPPPP – the price, which includes 2 decimal digits. If the value needs to be greater than 999.99 and/or has to be entered manually by the cashier, the 5 digits should be zeroes.
- C – Check digit for the bar code

Parameter	Description
Barcoded tender active	Select this option to activate the Coinstar barcoded tender.
Barcoded tender number	Enter the barcoded tender number between 1-99.
Barcoded tender prefix (2 digits)	Enter the barcoded tender prefix (2 digits, 10-99).
Barcoded tender value location	Enter the barcoded tender value location.
Barcoded tender value length	Enter the barcoded tender value length.
Additional Barcoded Tender Prefix	Enter the additional barcoded tender prefix to be used (2 digits, 10-99). If set to "0", the feature is disabled. (See above).

Signature Capture Tenders

This option leads to the parameters required for tenders that require signature capture.


To access this option, select Signature Capture Tenders from the menu in POST Parameter File 2. The Signature Capture Tenders screen displays.

ISS45 provides the ability to request signature capture on transactions charged to a customer's in-store account. This feature will facilitate store accounting and billing procedures. A reprint all of Accounts Receivable transactions (with signature) can be generated using the Connected Services Electronic Journal functionality.

Note:

As of this release, this enhancement is only available on systems using MicroTrax along with Verifone 7000 or Hypercom ICE 6000 (or ICE 5000) payment.

The following parameters designate up to 3 tenders that will support signature capture.



Signature Capture Tenders	
Signature Capture Tender Number 1	0
Signature Capture Tender Number 2	0
Signature Capture Tender Number 3	0

[F2] Update

Enter the numbers associated with in-house charge tender types. When these tenders are used the customer will be required to sign at the payments terminal so the signature can be captured. The signature will be captured locally and can be displayed within the Electronic Journal.

Gift Card Options

This option leads to the parameters required for Gift Cards.

To access this option, select Gift Card Options from Additional Tender Info menu in POST Parameter File 2. The Gift Card Options screen displays.

Note:

The Gift Card mechanism can also be configured to activate Phone Cards, either through a range of PLUs or Departments.

The screenshot shows a window titled 'PCM' with a sub-header 'Gift Card Options'. The main area contains the following parameters and values:

Parameter	Value
Gift Card in system.....	[N]
PLU Range.....	From 999999999999 To 9999999999
Department Range.....	From 0 To 0
Card value.....	From 1.00 To 5.00
PLU Number for recharging.....	100
Gift Card activation after tender.....	[N]
Parameters for StoreLine Payment:	
Allow offline gift card activation.....	[N]
Gift card activation tender number.....	25
Max number of gift cards purchased in single order.....	0
CC exceeding max gift cards in single order.....	0
Max amount for gift cards purchased in a single order.....	.00
CC exceeding gift cards amount in single order.....	0
CC for Price Override on Gift Card department range.....	0
Automatic tender of available balance for Gift Card.....	[]

At the bottom of the screen, there is a button labeled '[F2] Update'.

Parameter	Description
Gift Card in System	Select this option to acknowledge Gift Cards will be accepted.
PLU Range	Enter the beginning and ending PLU range for designated gift cards.
Department Range	Enter the beginning and ending department number designated for Gift Cards (for validation purposes). If a gift card PLU is attached to a department that is not defined in the new Gift Card Department Range an error message will display at the POS.
Card Value	Enter the beginning and ending range of gift card values.

Parameter	Description
PLU Number for recharging	Enter the PLU number used for adding value to a depleted gift card.
Gift Card Activation After Tender	For Barcode Types of "Gift Card Activation", check this box to initiate activation only after the transaction has been tendered.
Allow offline gift card activation	Select this option to allow gift card activation when communication with the EPS provider is down.
Gift card activation tender number	Enter the tender number assigned to gift cards.
Max number of gift cards purchased in a single order	Enter the maximum number of gift cards that may be purchased in a single transaction. The valid range is 0-99.
CC exceeding max gift cards purchased in a single order	Specify the control check to be issued when the maximum number of of gift cards purchased in a transaction is exceeded.
Max amount for gift cards purchased in a single order	Enter the maximum dollar amount of gift cards that may be purchased in a single transaction. The valid range is \$0.00 to \$9999.99.
CC for Price Override on Gift Gard department range	Specify the control check to be issued when a price override is attempted on a Gift Card item that is attached to a department within the Gift Card Department Range.

Note:

The feature does not apply to Gift Cards assigned by a PLU range.

Parameter	Description
	Note: If the issued control check is rejected, the Gift Card that triggered the control check (and exceeded the transaction limits for either quantity or amount) will not be sold. If both the quantity and dollar amount limits are set to 0 and \$0.00 respectively, and both control checks are set to "0", the cashier will be able to sell an unlimited number of gift cards with an unlimited accumulative value.
Automatic tender of available balance for Gift Card	Check this box to allow the available Gift Card balance to be approved with Host and returned for the amount available. If checked, the need to send a second approval request to MTXEPS when partially tendering a transaction with the card's available balance is eliminated.

Electronic Check Conversion

This option leads to the parameters required for Electronic Check Conversion (ECC).

To access this option, select Electronic Check Conversion from the Additional Tender Info menu in POST Parameter File 2. The Electronic Check Conversion screen displays.

PCM

Electronic Check Conversion

Electronic Check Conversion

ECC Tender Number 1.....0

ECC Tender Number 2.....0

ECC Tender Number 3.....0

Manual Check Tender Number.....0

ECC Template Name.....

[F2] Update

Tender Number allowed values: 0 - 25

An Electronic Check Conversion is similar to a debit card transaction. The customer hands the cashier a check. The check placed into the Printer/Scanner and returned to the customer after the sale is authorized and tendered. The customer's checking account is debited in approximately 2 days. An ECC transaction saves the store check handling fees and reduces cash turnaround time.

ECC is only supported for Tender Types of "Check". The EPS flag must also be set on the tender for ECC to work.

Note:

ECC will be protected by Bit 30 of the HASP plug.

Parameter	Description
ECC Tender Number 1	Enter the tender number for the first ECC tender.
ECC Tender Number 2	Enter the tender number for the second ECC tender.
ECC Tender Number 3	Enter the tender number for the third ECC tender.
Manual Check Tender Number	Enter the tender number for the manual ECC tender to use in situations where check conversion fails.

Parameter	Description
ECC Template Name	Enter the name of the template to print that will be printed at the end of the ticket when check conversion is successful (see below).

Biometric Options Parameters

This option leads to the parameters required for Biometric Options.

To access this option, select Biometric Options from the Additional Tender Info menu in POST Parameter File 2. The Biometric Options screen displays.

ISS45 supports PBT (Pay By Touch) biometric finger scanning as a tendering option. This solution allows a customer to initiate and tender a sales transaction with no physical documentation (i.e. loyalty card, tender, driver's license). In addition, ACH (Automated Clearing House) transactions can be handled through PBT.

ISS45 can also obtain customer birthdates and loyalty card numbers automatically from MTXEPS, in transactions where the finger scanning payment method is used. By implementing this feature, customer transactions are expedited by bypassing birth date and loyalty card prompting.

The TLOG will indicate if the media, loyalty card and/or birth date were obtained via PBT.

Note:

PBT data will not override the customer's loyalty card or birth date data if they are previously entered by the cashier within the transaction.

Biometric Options	
Use Biometric Identification functionality.....	[]
Display loyalty member name from Biometric Identification.....	[]
Retrieve DOB from Biometric Identification for age verification	[]
Retrieve loyalty information from Biometric Identification.....	[]
Display EFT payment icon on cashier display.....	[]
Customized EFT message on cashier display.....	[]
ACH Tender Number.....	0
[F2] Update	

Parameter	Description
Use Biometric Identification Functionality	This parameter defines whether the store uses fingerprint capture to access the customer's information for EFT payment, date of birth and/or loyalty card data. When checked, the POS will poll the EFT interface for customer information.
Display Loyalty Member Name from Biometric Identification	When checked, the member name returned from Biometric Identification will be displayed on the cashier display. This functionality is enabled when the "Retrieve loyalty information from Biometric Identification" parameter is checked.
Retrieve DOB from Biometric Identification for Age Verification	When checked, the birth date will be retrieved from Biometric Identification, if available. This functionality is enabled when the "Use Biometric Identification functionality" parameter is checked.
Retrieve Loyalty Information from Biometric Identification	When checked, the loyalty card number and member name will be retrieved from Biometric Identification, if available. This functionality is enabled when the "Use Biometric Identification functionality" parameter is checked.

Parameter	Description
Display EFT Payment Icon on Cashier Display	When checked, an EFT icon will be displayed on the cashier display when the customer has initiated any payment type on the EFT Pin Pad.
Customized EFT Message on Cashier Display	When checked, the POS application will echo the Pin Pad messages for the customer to the cashier display in a high granularity level.
ACH Tender Number	Enter the tender number to be used for ACH transactions (i.e. Check or Payroll Check).

FSA Options

The following parameters are related to Flexible Spending Arrangement (FSA) cards. The POS is able to accept these health-care debit account cards as a tender, separate prescription co-pay amounts from the other health-care qualified purchases and report them as separate totals to the EFT payment system.

PCM

FSA Options

Flexible Spending Account Options	
Enable Healthcare Item Substitution.....	[N]
Template Name for FSA Totals.....	_FSA_TOTAL
Template Name for FSA Disclaimer.....	_FSA_DISCL
Rx Print character.....	P
Non Rx Print character.....	H

[F2] Update

Parameter	Description
Enable Healthcare Item Substantiation	When this parameter is checked, FSA card processing is enabled.
Template Name for FSA totals	This parameter defines the template used to print Non-Rx, Rx and FSA totals on the receipt. If blank, these totals will not be printed.
Template Name for FSA Disclaimer	This parameter defines the template used to print an FSA disclaimer (on a separate slip) when an FSA tender is used in the ticket. If blank, this additional slip will not print.
Rx Print character	This parameter defines the character to print when an item has the Rx Item flag set in PLU Maintenance.
Non-Rx Print character	This parameter defines the character to print when an item has the Non-Rx Healthcare Item flag set in PLU Maintenance.

Trading Stamp Parameters

Trading Stamps may be awarded to customers according to the rules you specify. Use the feature's options and parameters to suit your specific requirements.

PCM Trading Stamp Parameters

Trading Stamps in system..... [✓]
 Purchase amount required for one stamp..... 1.00
 Multiplication calculation Method..... Dept. Eligible total[✓]
 Calculate qualifying total:
 Before vendor coupons..... [✓]
 Before bonus coupons..... [✓]
 Before store coupons..... [✓]
 Template name (text) to print on receipt..... TEMPLAT_03
 Don't display message on operator screen..... []
 Display/Print points with decimal point..... [✓]

[F2] Update

Parameter	Description
Trading Stamps in system	Check to enable Trading Stamps.
Purchase amount required for one stamp	Specify the purchase amount necessary to award one stamp. Example: If you specify \$5.00 and a customer's purchase totals \$10.00 then the system awards 2 stamps.
Multiplication calculation method	To award multiples of stamps, select the appropriate method. • None • Dept. Eligible Total • By Stamps earned

Note

In Department Maintenance, you must check the 'Trading Stamps eligible' parameter, for each department (as required), to participate in awarding of stamps.

The POS terminal multiplies stamps already awarded, by the multiplication factor, according to the method you select here.

Parameter	Description
Calculate qualifying total	You may optionally select any of the following options, as required: • Before vendor coupons • Before bonus coupons • Before store coupons The POS terminal awards stamps according to the purchase total, before or after coupons, as you specify here.
Template name (text) to print of receipt	Select the template (previously defined) to print the required 'stamps earned' message on the customer receipt. For more details on templates, refer to 'Templates/Multiple Part Receipts' in the Back Office reference Manual.
Don't display message on operator screen	Check this to avoid displaying the Trading Stamp message on the cashier screen.
Display/Print points with decimal point	Check this to display/print points with decimal point.

Multiple Stamp Schemes

Use the flexible options in Multiple Stamp Schemes to award customers with extra stamps.

PCM
Ver 7.8.3.0020 TIM'S MARKETS PC# 01 MFS1

Multiple Stamp Schemes

Scheme number.....>> 1
Active.....> [N]

Sun	Mon	Tue	Wed	Thu	Fri	Sat
[N]	[N]	[N]	[N]	[N]	[N]	[N]

Start time.....> 00:01
End time.....> 23:00

Minimum purchase.....> 1.00
Multiplication factor.....> 1.00

[F2] Update [F8] List [F9] Prev [F10] Next

07/16/2003 15:12:35 Copyright Fujitsu-ICL Inc.

You can set up schemes with different rules for various days and times.

- **To set up multiple stamp schemes**
- 1 From the Trading Stamps menu, select Multiple Stamp Schemes.
 - 2 Highlight a scheme number and select *Update*.
The Multiple Stamp Schemes update screen appears.

PCM
Ver 7.8.3.0020 TIM'S MARKETS PC# 01 MFS1

Multiple Stamp Schemes

Scheme number.....>> 1
Active.....> [N]

Sun	Mon	Tue	Wed	Thu	Fri	Sat
[N]	[N]	[N]	[N]	[N]	[N]	[N]

Start time.....> 00:01
End time.....> 23:00

Minimum purchase.....> 1.00
Multiplication factor.....> 1.00

[F2] Update [F8] List [F9] Prev [F10] Next

07/16/2003 15:12:35 Copyright Fujitsu-ICL Inc.

- 3 Accept the scheme number or enter another one.
- 4 Set up the following parameters as required

Parameter	Description
Active	Check to activate the scheme.
Sun - Sat	Check the required day(s).
Start time	Time to activate the scheme for the above day(s).
End time	Time to terminate the scheme for the above day(s).
Minimum purchase	The minimum purchase amount required to enable multiplication. If a customer buys for less than the specified amount, the number of stamps awarded is not multiplied.
Multiplication factor	The qualifying amount purchased (or number of stamps) is multiplied by the factor you enter here.

Receipt Printing Parameters

Receipt Printing Parameters enables you to control the different options available for printing on customer receipts.

Follow the parameters and descriptions below.

Receipt Printing Parameters	
1. Print currency symbol on receipt.....	[N]
2. Print "Bal. Due" each time subtotal is pressed.....	[]
3. Print "Bal. Due" after each tender.....	[]
4. Print coupons report on ticket.....	[N]
5. Print duplicate receipt on loans and pickups.....	[N]
6. Print separate receipts for each tender on pick-ups.....	[]
7. Print "PLU not found" slip.....	[N]
8. Print "PLU not found on inquiry" slip.....	[]
9. Print cashier name on receipt.....	[N]
10. Suppress printing points on receipt.....	[]
11. Print total items on receipt.....	With Bal. Due [N]
12. Additional template name to print on receipt bottom.....	BASHAS0001
13. Print saving totals on receipt when buffer printing is turned off..	[N]
14. Receipt Line Spacing.....	Reduced [N]
15. Print Tare Weight On Receipt.....	No [N]
16. Print customer slip after.....	0 customers.
17. Customer slip template name.....	
18. Minimum amount of transaction to be included in customer count	.00

[F2] Update

Parameter	Description
Print currency symbol on receipt	This parameter provides the option of printing the currency symbol (e.g., \$) on the customer receipt.
Print 'Bal. Due' each time subtotal is pressed	Check this so that 'Bal. Due' is printed every time the cashier presses the total key.
Print 'Bal. Due' after each tender	If checked, the balance due prints each time a different media is tendered. (part/multiple tendering) <i>Example</i> A customer purchases for \$60 and pays \$20 cash, \$20 check and \$20 credit card. The ticket prints the Balance Due after tendering with cash and check. The Balance Due will not print after tendering with the credit card as the customer does not owe any more money.
Print coupons report on ticket	Check this so that the coupons report is printed on the receipt.

Parameter	Description
Print duplicate receipt on loans and pickups	Check this so that whenever loans and pickups are done at the POS Terminal, a duplicate receipt prints.
Print separate receipts for each tender on pick-ups	Check this to print separate receipts for each different media on pick-ups.
Print 'PLU not found' slip	Check this in order for 'PLU not found' slip to print each time a PLU not found is entered at the POS Terminal.
Print 'PLU not found on inquiry' slip	If checked, and an inquiry is done at the POS Terminal against an item not found in the system, a separate slip will be printed after the customer receipt. The slip looks similar to the 'PLU not found' slip, and shows the number of the PLU not found.
Note	
This feature works only when an inquiry is done in the middle of a ticket. If an inquiry is done outside a ticket or as the first procedure at the start of a sale, the slip will not print.	
Print cashier name on receipt	Check this so that each time a pick up is performed at the POS Terminal for different media, separate receipts are printed for each media.
Suppress printing points on receipt	Check this to suppress printing of Member card points on customer receipts.
Note:	
If no member card is swiped, the 'sign up for member card' message will not appear.	
Print Total Number of Items on Receipt	This parameter provides the option to print the total number of items purchased on the customer receipt. Options are 'None', 'With Balance due' or 'On Separate Line'.
Additional template name to print on receipt bottom	If desired, select the template (previously defined) to print on the receipt bottom.

Parameter	Description
Print saving total on receipt when buffer printing is turned off	Check this to include savings total on the receipt when buffer printing is off. (See <i>Reorganize Receipt</i> for more information).
Receipt Line Spacing	Select the desired spacing between lines: Normal, Reduced or Compact.
Print Tare Weight on Receipt	This parameter provides the option of printing the tare weight on the receipt. Click the down arrow and choose: "No: (Do not Print)", "All" (Print All Tares) or "Manual (Print Manual Tares)".
Print Customer Slip After	This parameter enables the option to print a customer slip every X customers. Enter the number of positive tickets (up to 9999) to print before printing the Customer Slip Template. If set to 0, the feature is disabled.
Customer Slip Template Name	Enter the name of the defined template (under Templates/Multiple Part Receipts) to print at the bottom of the customer receipt after specified slip print interval (above) has been met.
Minimum Amount of Transaction to be Included in Customer Count	If the transaction sale amount (not including tax) meets or is exceeds the value in this parameter, customer count for slip printing will be incremented. Valid range is 0.00 - \$999.99.


Note:

If this parameter is to \$0.00, customer count will continue to increment with every ticket.

Q-Buster

Q-Buster allows you to use your IPAD to initiate customer checkout from outside the lane. Baskets are scanned into a suspended POS transaction using either a Q-Buster card or a member card. When the customer reaches the POS, the card is re-scanned to resume checkout.

Follow the parameters and descriptions below.




Parameter	Description
Q-Buster in system	Check this parameter to indicate that Q-Buster is implemented.
Use Member Card as Q-Buster Card	Check this parameter to indicate that customer member cards will be used in lieu of separate Q-Buster cards.

MobileLime

ISS45 supports a payment interface with MobileLime. MobileLime is a payment provider for stores where customers can pay for their purchases with their cell phone number.

Follow the parameters and descriptions below.



Parameter	Description
MobileLime Tender	Enter the MobileLime Tender Number.
MobileLime Discount Tender	Enter the MobileLime Discount Tender Number.
MobileLime Timeout	Enter the timeout (in seconds) before canceling the MobileLime transaction. A setting of "0" indicates no timeout is set.
MobileLime Prefix of Terminal ID	Enter the store's Terminal ID prefix number (which is used along with the lane number to form a unique identification code for each lane).
MobileLime Discount Number	Enter the ISS45 discount to be linked to the MobileLime Discount.

LaneHawk

LaneHawk is a solution from Evolution Robotics that uses digital video cameras and software to identify "when" and "what" items are on the bottom of a customer's cart. Using "visual pattern

recognition” for object recognition, Lane Hawk automatically detects and identifies “below the basket” items.

Follow the parameters and descriptions below.

LaneHawk Parameters

1. LaneHawk in system		[]
2. PortNumber		0
3. Heartbeat interval		0
4. LaneHawk timeout		0
5. LaneHawk alias in HOSTS file		

[F2] Update

Parameter	Description
LaneHawk in system	This parameter specifies whether LaneHawk is enabled at the POS.
Port Number	Use this parameter to define the TCP\IP port number for the LaneHawk server connection. Use a default of “2223” unless otherwise required by the store’s configuration.
Heartbeat interval	This parameter specifies how often (in seconds) heartbeat messages should be sent to the POS by the LaneHawk application. Use a default of “15” seconds unless otherwise required by the store’s configuration. A setting of 0 indicates heartbeat messages should not be sent.
LaneHawk timeout	This parameter specifies how long (in seconds) the LaneHawk application should wait for a heartbeat reply before dropping the connection and retrying. Use a default of “1” second unless otherwise required by the store’s configuration.

Parameter	Description
LaneHawk alias in HOSTS file	This parameter defines the LaneHawk server alias that will match the host file definition for IP resolution.

POST Configuration

The POST Configuration option serves to define such information as the peripheral equipment attached to a POS terminal, the keyboard layout to be used, and the header/footer to be printed on customer receipts. If many POS terminals are to have the same configuration, use the copy function, described further on, to save time setting them up.

To access this option, select POST configuration, from the System Parameters menu. The POST Configuration screen displays.

The screenshot shows the 'POST Configuration' window. At the top, it displays 'Ver 7.8.3.0020', 'TIM'S MARKETS', and 'PC# 01 MFS1'. The main area contains a table with the following data:

No.	H/F	Kbd	Scale	Display	Printer	Authorization
1	1	2	9000	No	Axiohm 7	None
2	1	2	None	No	Axiohm 7	None
3	1	2	9000	No	Axiohm 7	None
4	1	2	None	No	Axiohm 7	None
5	1	2	None	No	Axiohm 7	None
6	1	2	9000	No	EPSON H6	None
7	1	2	None	No	Axiohm 7	None
8	1	2	9000	No	Axiohm 7	None
9	1	2	MDL sca	No	Axiohm 7	None
10	1	3	9000	No	EPSON H6	None
11	1	2	None	No	EPSON H6	None
12	1	2	None	No	EPSON H6	None
13	1	2	9000	No	Axiohm 7	None
14	1	2	None	No	None	None
15	1	3	9000	No	EPSON H6	None
16	1	2	9000	No	EPSON H6	None
17	1	2	9000	No	Axiohm 7	None
18	1	1	None	No	None	None

On the right side of the table, there are three buttons: 'Update', 'cOpy', and 'Cancel'. The bottom of the window shows the date '07/17/2003', time '11:49:49', and copyright 'Copyright Fujitsu-ICL Inc.'.

This screen lists the POS terminals and shows the basic components of each POST configuration.

Use the *PgUp*, *PgDn*, *Up Arrow* and *Down Arrow* keys to page through the list.

Functions available from this screen are *Update* and *cOpy*.

➤ **To define or update a POST configuration**

- 1 Highlight the required POS number and select *Update*. The POST Configuration 1 screen displays.

PCM Ver 7.1.3.0120 TIM'S MARKETS PC# 01 MFS1

POST Configuration 1

POS number.....▶ **1** CDS Active []
 POS type.....▶ 5000 [↓]
General:
 2X20 kbd. display.....▶ []
 Generate sound from.....▶ Keyboard [↓]
 Battery backup.....▶ []
 Monitor type.....▶ UGA Color[↓]
 Touch screen type.....▶ None [↓]
 Weight on TeamPOS.....▶ [✓]
 Port for print commands▶ None [↓]
 Drawer in use.....▶ [✓]
 connected to printer▶ []
 Dual drawer enabled..▶ []
Scanner:
 COM.....▶ 0
 IRQ.....▶ 0
 Baud Rate.....▶ None [↓]
 Data Bits.....▶ 0
 Parity.....▶ None [↓]
 Handshake.....▶ []
Scale:
 Type.....▶ Scan/Scale single[↓]
 COM.....▶ Com 4 [↓]
 IRQ.....▶ 5
 Baud Rate.....▶ 9600 [↓]
Printer:
 Type.....▶ EPSON H6000 [↓]
 Port.....▶ None [↓]
 MICR reader in use.....▶ [✓] OPOS..▶ [✓]
 Enable Check Flip.....▶ []
Customer Display:
 COM.....▶ 0
 IRQ.....▶ 0
 Type.....▶ None [↓]
 Baud rate.....▶ None [↓]

[F2] Update [Auth/APT] [F6] Next Page [F9] Prev [F10] Next

04/29/2010 13:35:54 Copyright StoreNext

- 2 The number of the selected POST displays in the POS Number field. Press *Enter* to continue.
- 3 The POS type displays. From the drop-down list, select the terminal type and press *Enter*.
- 4 In each of the following fields, select one of the available values from the drop-down lists by pressing the *Right Arrow*, or check the appropriate parameters.

Value	Description
General:	
2X20 Kbd Display	Check if the cashier's LCD display is connected to the keyboard.


Value	Description
Generate sound from	To specify where the beep sound will come from, press the <i>Right Arrow</i>. A drop-down list displays the components from which the beep sound may originate. Keyboard - The beep sound will be heard from the keyboard alone. PC (Sound or Beep) - The sound or beep sound will come from the PC itself. Keyboard and PC - The cashier will hear the beep from the keyboard as well as the PC, presuming they both have 'beepers'. PC Sound – The cashier will hear sounds from both the Touch Screen speaker and the PC Sound Card (through external speakers). A positive confirmation tone will emit on a successful sale of Item / Department / Weight PLU, a negative tone for an error and a keystroke sound for any pressed menu key or touch screen key. Note: This parameter is useful when the keyboard is installed at a distance from the PC and cashiers may not hear a PC-generated beep, or if the keyboard has no 'beeper' inside.
Battery Backup	Check this parameter if a backup battery pack is installed.
Monitor Type	Select either VGA black & white or VGA color.
Touch Screen Type	The system supports two different touch screen types to activate soft keys. In Post Configuration select either SNIkey or Dynakey from the drop-down list. If the Touch Screen type selected is 'Snikey', the active keys on the POS are <i>Shift F2</i> through <i>Shift F7</i>. If the Touch Screen type is 'Dynakey', the active keys are <i>F2</i> through <i>F7</i>.
Weight on TeamPOS	If a scale is connected, check this parameter to have a scale display on the cashier's CRT. The number of items (top right corner of screen) can not be displayed if you use this option.

Value	Description
Port for print commands	During buffer printing, print commands are sent to the printer at the end of the ticket. However, this new parameter allows the print commands to be sent simultaneously to the selected port at real time. Note Print Commands are sent to the specific port only when buffer printing is active.
Drawer in use	Indicate whether or not a cash drawer is attached (Yes or No).
Connected to printer	Check this if the drawer is connected to the printer.
Dual Drawer in use	Check this to enable the use of two drawers at the PoS terminal. Use of a special cable is required.
Printer:	
Type	The printer connected to this POST. The Axiohm 4101 printer does not have a built in paper guillotine, it has a 'tear bar' whereby the paper is manually torn off after every ticket. A message appears on the POS Terminal prompting the cashier to tear off the customers receipt at the end of each ticket. If the cashier does not tear off the customer's receipt within 30 seconds, the printer marks the receipt paper with a line of asterisks so that a manual tear may be done at a later stage.
Port	This enables you to connect an RS232 printer to a port other than the default. Note Set your printer port only if you are working with a port other than the default used by the application. Leave the printer port option set to None, if you are working with the default printer port.
MICR reader in use	Check if Magnetic Ink Check Reader is in use.

Value	Description
Enable Check Flip	Select this option if you want the printer to flip the check automatically.
	Note Check endorsements on IBM 4610 printers endorse the back of check using the following: (1) MICR Read, (2) Endorse Back, (3) Flip Check and (4) Endorse Front. The Printer Type needs to be set to "IBM 4610" and the OPOS checkbox needs to be checked.
Scanner:	
COM	Select the com 0-10 to which the scanner is connected.
IRQ	Refer to scanner documentation for the possible interrupt requests. Beware of IRQ conflicts with other peripherals.
Baud	From the drop down list, select either one of the following: • None • 2400 • 4800 • 9600 • 19200 • 38400
Data Bits	Enter the required scanner bits. Refer to your scanner manual for settings.
Parity	Use the right arrow to see the available options: • None • Odd • Even Select the applicable parity option, according to your scanner manual.
Handshake	Check this parameter to establish DTR (<i>Data Terminal Ready</i>) type handshake.
Scale:	
Type	The type of scale being used at this POS.
COM	Select the appropriate communication port.

Value	Description
IRQ	Refer to scale documentation for the possible interrupt requests. Beware of IRQ conflicts with other peripherals.
Baud Rate	Refer to scale documentation for the appropriate baud rate.
Customer Display:	
COM	Specify the appropriate communication port.
IRQ	Enter the possible interrupt requests. Beware of IRQ conflicts with other peripherals
Type	Select the appropriate option: • None • ICL Standard • SNI Standard
Baud Rate	Refer to scale documentation for appropriate baud rate.

Press <Alt><A> to configure the Authorization and APT settings.



- Type Select the desired authorization type:
- None
 - SMT
 - NTN
 - EFT
- Port Select the appropriate comm. port.
- Baud Rate Type in the baud rate according to the device.
- Type Select the appropriate Interface Type:
- None
 - Zinetix
 - Catalina
 - Catalina Local
 - Catalina Global
- Port Select the appropriate comm. port.
- Baud Rate Type in the baud rate according to the device.
- StoreLine EPS Select the appropriate PinPad Type:
- PinPad Type
- None
 - Concord
 - enTouch1000
 - enCrypt2100

Press *F2* to save the settings.

Press *F6* to move to the next screen.

PCM
Ver 7.1.0.0031 TIM'S MARKETS PC# 01 MFS1
POST Configuration 2

POS number.....> 1
Header/Footer.....> 1
Keyboard type.....> 2 Keyboard port.....> 7
Graphic logo.....> 2
Debug mode.....> No [↓]
Minimum amount in drawer.....> .00
CC for minimum amount in drawer.....> 0
Maximum amount in drawer.....> .00
CC for maximum amount in drawer.....> 0
Bagger ID.....> []
Print text to transaction file.....> [✓]
EFT location.....> 0
Allow EFT reconciliation.....> []
Display queue length every 'n' minutes.....> 0 [↓]
Queue length threshold alert (count).....> 0
Checkout bank.....> 0
POS O/S type.....> WinPOS [↓]

Self Checkout:
Type.....> None [↓]
Cashier.....> 0
POS.....> 0

[F2] Update [F5] Prev Page [F8] List [F9] Prev [F10] Next

07/12/2005 12:48:50 Copyright Fujitsu-ICL Inc.

- 5 The Header/Footer field displays the number of the header/footer linked to this POS. Headers/footers are assigned to POS terminals via the Receipt Header/Footer Maintenance option (see 'Receipt Header/Footer Maintenance', later in this manual). If necessary, change this assignment: overtype another header/footer number, or press *F8* to select one from the list window.
- 6 In each of the following fields, select one of the available values from the drop-down lists by pressing the *Right Arrow*, or check the appropriate parameters.

Value	Description
Keyboard Type	Keyboard layouts are linked to POS terminals via the POS Keyboard Programming option (see 'POS Keyboard Programming', later in this manual). If necessary, change this assignment: overtype another keyboard number, or press <i>F8</i> to select one from the list window.
Graphic Logo	Type in (or update) the graphic logo number to be used. (See 'Graphic Logo Maintenance' later in this chapter). Logos print above the header message on the customer receipt. Logos are not mandatory.
Debug Mode	Indicate whether the terminal works in debug mode (Yes or No).
Minimum Amount in Drawer	Enter the amount to trigger the 'Top Up' message on the POS terminal. Whenever the total of all participating tenders drops to this amount or below, the Top Up message displays on the POS terminal cashier display.
CC for Minimum Amount in Drawer	The control check to display when the cash in drawer amount is equal to or less than, the minimum amount specified.
Maximum Amount in Drawer	Enter the amount to trigger the 'Assistance' message on the POS terminal. Whenever the total of all participating tenders meets or exceeds this amount, the Assistance message displays on the POS terminal cashier display.

Value	Description
CC for Maximum Amount in Drawer	The control check to display when the cash in drawer amount is equal to or more than, the maximum amount specified.
Bagger ID	Check this parameter to force the cashier to enter the bagger ID when the <i>Total</i> key is pressed. Once the bagger ID is entered, the prompt does not display again within the transaction. For more information, see the WinPOS User Guide.
Print Text to Transaction File	Check this to see text transactions in the Electronic Journal.
EFT Location	This is a unique ID number for the POS terminal. During EFT transactions, this location number is transmitted to the bank.
Allow EFT reconciliation	Allows the store to reconcile and balance the figures according to the store's records, with information from the bank.
Display queue length every 'n' minutes	From the drop down list, select the number of minutes for the 'Queue Length' prompt to display on the POS Terminal . (This information will display to the Pocket Office Dashboard Module User).
Queue length threshold alert (count)	Enter in the Queue Length limit to trigger an alert message at the Back Office.
Checkout bank	Select the number of the checkout bank from the list.
POS O/S Type	Select the POS Operation System (DOS, WinPOS, etc).
Keyboard Port	Enter the Com Port (1 to 10) used by the POS Keyboard.
Self Checkout:	
Type	Specify the type of Self Checkout system: None, PSI or NCR Scot.
Cashier	Specify the cashier number assigned to the Self Checkout terminal.
POS	Enter the designated Self Checkout POS terminal number.

7 Press *F2* to update the definition.

➤ **To copy a POST configuration to another POST**

- 1 From the POST Configuration screen, highlight the POS number to copy.
- 2 Select *Copy*. A pop-up screen prompts you to enter the record number (POST number), to copy the selected configuration to.
- 3 Enter the required record number and press *Enter*. The target POS number now has the same configuration as the source POS.

Repeat the above steps as many times as necessary, until all POS terminals are configured.

Displaying Another POS Terminal

- Type in the POST number and press *Enter*.
- Press *F10* to display the next POST. Press *F9* to display the previous POST.


Checkout Bank Groups

Checkout bank groups are logical or physical groups of PoS terminals. A typical store may consist of a main row of checkouts (*front end*), as well as various satellite terminals located in different areas of the store.


The Checkout Bank Group option lets you set up groups and give them names or descriptions to suit your environment.

➤ **To set up a checkout bank group**

- 1 From the POST Configuration menu, select Checkout Bank Groups.
The Checkout Bank Groups list appears.



- 2 Highlight the required Group number and description, and select *Update*. The Checkout Bank Groups screen appears.



- 3 Enter an appropriate checkout bank number and description.
- 4 Enter the maximum percentage of POS terminals to be upgraded for this checkout bank at one time, through Code Distribution.

- 5 To link PoS terminals to the checkout bank, click *Linked POS*.
The PoS selector dialog appears.
- 6 Select the PoS terminals to link and press *Enter*.
- 7 Click *F2 Update* to save.

Coupon Parameters

This option provides access to parameters needed to link coupons to the appropriate tender numbers, and coupon printing.

These parameter settings provide the system with such information as:

- Coupon days.
- Validity ranges.
- Minimum order amounts.
- Level of coupon validation.
- Coupon taxability.
- Whether coupons are netted from totals.

To access the option, select Coupon Parameters from the System Parameters menu. The Coupon Parameters menu displays.



Each option on this menu leads to a screen containing a group of parameters. Select the required option to display the appropriate screen. Refer to the relevant section below for parameter descriptions.

Coupon Parameters 1

ISS PCM

Ver 7.8.3.0020 TIM'S MARKETS PC# 01 MFS1

Coupon Parameters Page 01

Level of coupon validation..>Family <all 3 digits>[↑↓]

Tax Forgive:

	1	2	3	4	5	6	7	8	
Vendor coupon..>	[]	[]	[]	[]	[]	[]	[]	[]	Dept net..>[]
Store coupon..>	[✓]	[✓]	[✓]	[✓]	[✓]	[✓]	[✓]	[✓]	Dept net..>[✓]
Bonus coupon..>	[✓]	[✓]	[✓]	[✓]	[✓]	[✓]	[✓]	[✓]	Dept net..>[✓]

[F21 Update]

07/21/2003 07:50:07 Copyright Fujitsu-ICL Inc.

Define the following parameters.

Parameter	Description
Level of Coupon Validation	The type of validation to be performed for vendor, store and bonus coupons. The possibilities are: - None: Coupons are not validated at all. - Manufacturer: A vendor coupon must match the item's manufacturer code. - Family (1 digit only): The coupon must match the manufacturer code and the first digit of the family code of the item. - Family (all 3 digits): The coupon must match the manufacturer code and all three digits of the item's family code. Press the <i>Right Arrow</i> to open the drop-down list and select the required option.
Tax Forgive	If any of the coupon types, vendor, store and bonus, is exempt from a tax rate, check the corresponding tax box. For example, if vendor coupons are exempt from tax rates 6, 7 and 8, check the boxes 6, 7 and 8 on the vendor coupon line.

Parameter	Description
Dept Net	This parameter relates to Net Daily sales totals in department reports when coupons are tendered as part of the sale. There are three such parameters, one for each type of coupon: vendor, store and bonus. If vendor, store and bonus coupons should be included in the Net Daily department sales totals, leave the check boxes blank. For example, if store coupons and bonus coupons should be deducted from the Net Daily department total, check the Store coupon and Bonus coupon Dept Net parameters.

Coupon Parameters 2

Parameter	Value
1. Give bonus coupons on discountable items only.....	[]
2. CC to allow coupons to bring Subtotal < Zero.....	20
3. CC to allow more coupons than items.....	21
4. Allow coupons in departments with no sales in order.....	[N]
5. Maximum coupon face value.....	10.00
6. Tender number for vendor coupons.....	10
7. Tender number for store coupons.....	11
8. Tender number for bonus coupons.....	15
9. Tender number for UPC 5 coupons.....	22
10. Tender number for EAN 99 coupons.....	18
11. CC to restrict redemption of EAN 99 coupons out of sale...	0
13. CC to allow coupon as first item in the ticket.....	0
14. No keyboard sound for coupons without department or price.[N]	
15. Markdown department for UPC5 coupons with 992 bypass code. 1 GROCERY[4]	
16. Validate EAN99 as UPC5.....	[N]

IF21 Update

07/21/2003 07:58:22 Copyright Fujitsu-ICL Inc.

Define the following parameters.

Parameter	Description
Give Bonus Coupons on Discountable Items Only	Check this parameter to allow bonus coupons only for discountable items whose Discount Prohibited parameter (in the item record) is not checked. Leave blank to apply bonus coupons to any item.
CC to Allow Coupons to Bring Subtotal < Zero	If a control check is specified here, then it's triggered when a coupon amount is greater than the balance due.
CC to Allow More Coupons than Items	Specify the relevant control check to trigger if number of coupons exceeds the number of items in a transaction.
Allow Coupons in Departments with No Sales in Order	Check this parameter to allow coupons in a transaction without items.
Maximum Coupon Face Value	Maximum dollar value that a coupon may have when its price is manually entered (the amount printed on coupon face).

Parameter	Description
Tender Number for Vendor, Store and Bonus Coupons	The tender number of vendor, store, and bonus coupons must be specified here, so that coupons can be accurately reported in the system. Tender types for coupons are defined in the Tender Types file (see 'Tender Types', in the File Maintenance chapter). Even though tender records are set up for these coupons, these tender numbers may not be used with the <Tender> key on the registers. Store and Vendor Coupons are defined in the PLU file.
Tender Number for UPC5 coupons	The tender number for UPC5 type coupons must be specified here. See 'Tender Types' in the File Maintenance chapter.
Tender Number for EAN 99 coupons	The tender number for EAN 99 coupons.
CC to restrict redemption of EAN 99 coupons out of sale	Enter the Control Check number in order to restrict redemption of EAN 99 coupons out of sale.
CC to allow coupon as first item in the ticket	Specify the control check to trigger if a coupon is the first item entered on the POS terminal.
Note If the first item in the ticket is a coupon, only coupon entries are allowed in the transaction.	
No keyboard sound for coupons without department or price	Check this to suppress the keyboard sound when coupons without department or price are sold at the POS Terminal.
Markdown department for UPC5 coupons with 992 bypass code	Enter the department number to be marked down for UPC5 coupons with 992 bypass code
Validate EAN99 as UPC5	Select this checkbox so that the system interprets every PLU starting with 99 as a UPC5 coupon and not as an item.

Coupon Parameters 3

PCM Coupon Parameters Page 03

Bonus Coupon Options:

Range	Cpn. Mult.	Add. Amount	Cpn. Value From	To	Min Order	Tend No.	Ceiling Amount
1	100	.00	.05	.50	.00	15	.00
	Sun Mon Tue Wed Thu Fri Sat						
	[X] [] [] [] [] [] []						
2	.00	.00	.00	.00	.00	0	.00
	Sun Mon Tue Wed Thu Fri Sat						
	[] [] [] [] [] [] []						
3	.00	.00	.00	.00	.00	0	.00
	Sun Mon Tue Wed Thu Fri Sat						
	[] [] [] [] [] [] []						
4	.00	1.00	.00	.00	.00	0	.00
	Sun Mon Tue Wed Thu Fri Sat						
	[] [] [] [] [] [] []						

[F2] Update

This screen serves to define bonus coupons. Bonus coupons are calculated against vendor coupons and charged to a store. Vendor coupons give double, triple or any specified multiple of bonus coupons if a specified dollar limit has been reached, and the day of the week is a bonus day. Ranges of coupon values to allow for multiples of bonus coupons may be specified.

You can define up to four ranges. For each range, enter the following information.

Parameter	Description
Coupon Mult.	The number by which the vendor coupon is multiplied. For example, if vendor coupons should be doubled, enter 2.
Add(itional) Amount	This is an optional additional amount, above and beyond the 'ceiling amount'.
Coupon Value From-To	The beginning and end numbers of the bonus coupon range.
Minimum Order	The minimum purchase amount required for a coupon in this range to be issued.
Tender Number	Specify the tender type for tracking the bonus amount on receipt and in reports.

Parameter	Description
Ceiling Amount	Specify the maximum value allowed when combining the value of the Manufacturer's coupon with the value of the Bonus Coupon. (Vendor + Bonus amount)
Sun - Sat	Check the days on which the coupons should be issued. For example, if the coupon range is to be issued only Fridays and Saturdays, check the Fri and Sat boxes.

Coupon Parameters 4

This option contains parameters for defining UPC5-type vendor coupons.

PCM
Ver 7.8.3.0020 TIM'S MARKETS PC# 01 MFS1
Coupon Parameters Page 04

Code	Type	'BUY' Qty	'GET' Value
00	1 Key in value	0	.00
01	1 Key in value	0	0.00
02	4 Buy X or more, get 1 free	0	0.00
03	5 Get Y amount off	0	1.10
04	5 Get Y amount off	0	1.35
05	5 Get Y amount off	1	1.40
06	5 Get Y amount off	0	1.60
07	7 Buy X or more, get Y amount off	3	1.50
08	7 Buy X or more, get Y amount off	2	3.00
09	7 Buy X or more, get Y amount off	3	2.00
10	5 Get Y amount off	0	0.10
11	5 Get Y amount off	0	1.85
12	5 Get Y amount off	0	0.12

[F2] Update

07/21/2003 08:11:15 Copyright Fujitsu-ICL Inc.

0 Not in use
1 Key in value
2 Get 1 free
3 Buy X, Get 1 free
4 Buy X or more, Get 1 free
5 Get Y amount off
6 Buy X, get Y amount off
7 Buy X or more, Get Y amount off

The column on the left side of the screen provides a list of coupon type codes. These 2-digit code numbers are used to identify the type of discount or offer on each coupon.

Use the *PgDn* and *PgUp* keys to page through this list. For coupons that have not been defined, the message 'Not in use' appears on the screen.

➤ To define a coupon type

- 1 Move the cursor to the relevant line.
- 2 Enter a type code from the list on the right, and press *Enter*. The following types are available:

00 - Not in use

01 - Key in value (coupon without value, key in amount manually)

02 - Get 1 free

03 - Buy X get 1 free

04 - Buy X or more, get 1 free

05 - Get Y amount off

06 - Buy X, get Y amount off

07 - Buy X or more, get Y amount off

X denotes the quantity to be purchased in order to get a coupon. If you selected any one of the options containing X, you need to enter the quantity in the BUY Qty field.

Y denotes amount to be reduced from sale. If you selected any one of the options containing Y, you need to enter the amount in the Get Value field.

- 3 In the Buy Qty field, enter the quantity to purchase in order to get a coupon.
- 4 In the GET Value field, enter the amount to be reduced from sale. (Do not enter an amount if the coupon type is defined as 'get one free'.)
- 5 Press *F2* to record the definition.

Coupon Printing Parameters

Coupon Printing Parameters option enables you to define and design store coupons to be printed for each customer transaction based on the items in that basket.

PCM

Coupon Printing Parameters

Coupon Printing Options:

1. Coupon printing in use.....	[X]	
2. Maximum number of coupons to print per transaction.....	2	
3. Minimum purchase amount required.....		1.00
4. Control Check for minimum purchase.....	0	

[F2] Update

Parameter	Description
Coupon Printing in use	Check this if coupon printing is used in the system
Maximum number of coupons to print per transaction	Enter in the maximum number of coupons to print per transaction.
Minimum purchase amount required	Enter in the minimum purchase amount required to enable coupon printing.
Control check for minimum purchase	Enter the control check number to trigger for minimum purchase.

The parameters on this screen are used for controlling coupon printing at POS terminals.

Coupon Printing Maintenance

The Coupon Printing option enables you to define and design store coupons to be printed for each customer transaction based on the items in that basket. A customer has the right to a coupon based on such conditions as:

- Purchasing a specific item.
- Purchasing an item from a specific department.
- Not purchasing a specific item.
- Not purchasing an item from a specific department.

A coupon prints in a 5 line format at the end of a customer transaction. Coupon printing is controlled by a number of parameters. See the section 'Coupon Printing', earlier in this chapter.

No.	In Use	Item/Department	Item/Dep Num	Barcode	Logo
9982	[✓]	DEPARTMENT	0	0	0
9983	[✓]	DEPARTMENT	0	0	0
9984	[✓]	DEPARTMENT	0	0	0
9985	[✓]	DEPARTMENT	0	0	0
9986	[✓]	DEPARTMENT	0	0	0
9987	[✓]	DEPARTMENT	0	0	0
9988	[✓]	DEPARTMENT	0	0	0
9989	[✓]	DEPARTMENT	0	0	0
9990	[✓]	DEPARTMENT	0	0	0
9991	[✓]	DEPARTMENT	0	0	0
9992	[✓]	DEPARTMENT	0	0	0
9993	[✓]	DEPARTMENT	0	0	0
9994	[✓]	DEPARTMENT	0	0	0
9995	[✓]	DEPARTMENT	0	0	0
9996	[✓]	DEPARTMENT	0	0	0
9997	[✓]	DEPARTMENT	0	0	0
9998	[✓]	DEPARTMENT	0	0	0
9999	[✓]	DEPARTMENT	0	0	0

The Coupon Printing File screen lists all the coupons in the coupon printing file, showing the following information per record:

- Coupon number.
- In use: if the coupon is currently in use, it's marked by a check sign [✓].
- Item/Department: basket will be searched for Item or Department, for this coupon.

- Item/Department Number
- Barcode Number
- Graphic Number

Adding a New Coupon

This function allows you to define and design a new store coupon.

- 1 Highlight one of the blank lines in the Coupon Printing File screen, and select *Update*. The Coupon Printing - Insert/Update screen displays.

The screenshot shows the 'Coupon Printing Maintenance' window. The title bar says 'PCM' and 'Coupon Printing Maintenance'. The main area is a list of fields with their current values and options. The fields are: 'Coupon number[1-100]' with value '3', 'Coupon in use' with value '[]', 'Ticket amount to print coupon' with value '.00', 'Item/Department' with value '[]', 'Item/Department found/not found in basket' with value '[]', 'Minimum purchase amount required' with value '.01', 'CC for minimum purchase' with value '17', 'Show the above CC if ticket amount is less than the minimum purchase amount by' with value '2.00', 'Print barcode' with value '[]', 'Barcode number' with value '9900000000004', and 'Graphic logo' with value '0'. The 'Coupon Text' section shows 'STORE COUPON .10 OFF HAVE NICE DAY!'. The right side has buttons for 'checkK digit', 'Center Text', '[F2] Update', '[F8] List', '[F9] Prev', and '[F10] Next'.

- 2 The Coupon Number already displays. Type in another number, if necessary. Press *Enter* to continue.
- 3 Fill in the required fields as explained in the following table.

Field	Description
Coupon in Use	Check or uncheck to enable or disable the coupon. The coupon will be printed on each register as per system setup.

Field	Description
Ticket Amount to Print Coupon	Use this parameter to make the system look at the amount you enter here as the qualifier. The system will not check if items are found or not found in the transaction.
Item/Department	Item - the basket will be searched for a specific item. Department - the basket will be searched for a specific department.
Item/Department Number	If the coupon is item specific, enter the PLU number of the item. If the coupon is department specific, enter the department number. Type in the number or, press <i>F8</i> to display a list of items or departments and select the required value.
Item/Department Found/Not Found in Basket	Found – Check this field so if the item or department is found in the basket, that particular coupon prints on the register. Not Found – Leave this field blank so if the item or department is not found in the basket, the coupon prints on the register.
Minimum Purchase Amount Required	Customer must spend the minimum amount you enter here, to qualify for the coupon.
CC for Minimum Purchase	Control check to trigger if minimum purchase amount (above) not met.

Field	Description
Show the above CC if ticket amount is less than the minimum purchase amount by	The CC above will be triggered when the 'Total Ticket' amount is less than the 'Minimum Purchase amount required' (defined above) minus the amount defined in this parameter. For Example: - Min Purchase Amnt Req. = \$10.00 - This Parameter set to = \$3.00 - Ticket Total = \$7.00 (\$10.00-\$3.00)=\$7.00 The CC appears until ticket total amount reaches \$10.00
Print Barcode	Check this parameter to enable barcode printing on the coupon. Note Barcodes can be printed only if you use thermal receipt printers.
Barcode Number	If the Print Barcode parameter is checked, type in the required barcode number, up to 13 digits. If the system is operating without check digit validation, the POS terminal adds a valid CD to the barcode number when it prints. If the system is operating with check digit validation, the POS terminal checks if the barcode has a valid CD and prints only if a valid CD exists. Select <i>check digit</i>. The system calculates and inserts the check digit.
Graphic Logo	Select the graphic logo number from the list.

- The actual text to be printed on the coupon is entered in the coupon text lines. Use the *Enter* or *Tab* key to move the cursor to the first text line. You can type up to five lines of text. Type in the text of the first line as it should appear on the coupon. Press *Enter*.
- If you want this text line to print in boldface, press the *Right Arrow*. A drop-down list displays Normal and Bold. Highlight

Bold and press *Enter*. Press *Enter* again to continue to the second line. If the text should print in normal characters, just press *Enter* to continue.

- 6 If you want to center the text on a specific line, highlight that line and do one of the following:
 - Activate the Center Text function by pressing *Alt+C* or,
 - Use the *Tab* key to select the function button and press *Enter* to activate it.
- 7 Repeat steps 4 - 6, for each text line.
- 8 Press *F2* to record the coupon definition.

Other Functions

In this screen, you can use the same functions as those described in 'Updating a Coupon'.

Updating a Coupon

This function allows you to update a coupon definition.

- 1 To update the details of a coupon, highlight the coupon in the Coupon Printing File screen, and select *Update*.

The Coupon Printing - Insert/Update screen displays with the details of the selected coupon. For field descriptions, see 'Adding a New Coupon' earlier in this chapter.
- 2 To enter new/updated data in a field, move the cursor to that field, using the *Enter* or *Tab* key. Type or overwrite the new data. If the field has item selection, press *F8* to select a new value.

➤ **To display another coupon**

Type in the coupon number and press *Enter*; or

➤ **To page through coupons**

Press *F10* to display the next coupon. Press *F9* to display the previous coupon.

Transaction Handling Parameters


This option allows you instruct the system how to handle transactions from POS terminals, in the event of the POS terminal

being off-line at **End of Day**. For example, a comms board might be faulty and cannot be replaced until the next day, or a terminal has been used for a 'side-walk sale' and is not connected to the network before End of day.

Note

If you choose not to check the options available, data for the current day is lost from any POS terminal not communicating with the servers when End of Day is run.

To access the option, select Transaction Handling Parameters from the System Parameters menu. The Transaction Parameters screen displays.



Parameter	Description
Transaction Version	The transaction version number, which automatically increments with every End of Day process. The version number is informative only - it cannot be edited.
Process PLU transactions	Check this option if you want PLU movement updated. (Stock control).

Parameter	Description
Process Memory	Check this if you want to print on-line reports with the current days' data.
Process Cashier	Check this if you want to keep cashier totals in the system. Any amounts that appear over today, will be short the next day, and vice versa.

Press *F2 Update* to record the definition. At the prompt, select *Yes* to accept changes, or *No* to reject changes. The System Parameters menu displays.

Design POS Menu


This option allows you to customize the options listed in the POS terminal Back Office menus. Only authorized personnel may use this program. The functions available are those specified in Function Maintenance.

Use this program to list different options for the POS when in *closed* mode (signed-off), in *sales* mode (signed-on) and *supervisor functions* (signed-on or off).

To allow terminal operators to display the POS terminal back office menus, a back office menu key must be defined on the keyboard. See the section on POS Keyboard Programming, later in this manual.

The Back Office menu on the POS is updated automatically when changes are made on the MFS computer.

To access the option, select Design POS Menus from the System Parameters menu. The Design POS Menu displays.



There are three choices: POS Closed Menu, POS Sales Menu and Supervisor Menu.

POS Closed Menu


To design the POS Closed menu, select POS Closed Menu. The Design POS Closed Menu screen displays.

Line	Function	Keylock	Privilege
1	809 ADD LOAN	0	0
2	816 SIGN ON/OFF	0	0
3	838 KEY_RECORD	0	0
4	806 X READ REPORT	0	0
5	807 TRAINING MODE	0	0
6	839 KEY_PLAYBACK	0	0
7	984 EVENT GENERAL VOID	0	0
8	811 MANUAL END OF DAY	0	0
9	813 CHANGE PASSWORD	0	0
10	827 LOAD HEADER FROM MFS	0	0
11	830 PIP EXIT	0	0
12	831 DEPARTMENT REPORT	0	0
13	836 ZERO SCALE	0	0
14	916 LOAD/UPDATE PLU FILE	0	0
15	814 TAX REPORT	0	0
16	1028 SUSPEND/RESUME_PRINT	0	0
17	701	0	0
18	845 DISPLAY DRAWER ALLOC	0	0

07/21/2003 11:47:58 Copyright Fujitsu-ICL Inc.

Adding a new menu option


- To define a new menu option
 - 1 Highlight the line number where you want the option to appear on the B/O (Back Office) Menu.
 - 2 Press *F8 List* to show the available functions to choose from.



- 3 Scroll the list and press *Enter* to select the required function.
- 4 Press *Tab* or *Enter*. The selected function displays and the cursor moves to the Keylock field.
- 5 Type in the Keylock position required, from 1 to 5. Press *Tab* or *Enter* and type in the required cashier Privilege number.
- 6 Select *F2 Update* to record the definition.

Note

Use the *F4 Other Menu* button, to see what functions are defined for the POS Sales Menu. (When you're editing the POS Sales Menu, activating this button displays the POS Closed Menu definition.)



➤ **To edit/change a menu option**

The procedure is the same as for defining a new menu option, above.

➤ **To delete a menu option**

- 1 Highlight the option you want to delete.
- 2 Type in 0 (zero) and press *Enter*.
- 3 Select *F2 Update* to record the definition.

POS Sales Menu

Menu options for the POS Sales Menu are the same as for the POS Closed Menu. The only difference is that options defined here are for the POS Terminal in signed-on mode.

POS Supervisor Menu

Menu options for the POS Supervisor Menu are the same as for POS Closed and Sales Menus. You can insert the supervisor menu option on both the POS Closed and POS Open menus.

To prevent unauthorized use of the Supervisor menu, use keylock position options and privileges, as appropriate.

Cost Plus Programming

This option allows you to set up parameters if your store operates on a 'Cost-Plus' system. In a cost-plus situation, some (or all) items are sold at their cost price plus a specific percentage, which is dependent on the total amount purchased by a customer. The more a customer buys, the lower the percentage mark-up added to the cost price total.

To make use of this system, you must check the Cost Plus parameter in General POST Parameters 2. (Earlier in this chapter.)

To flag *items* for sale at cost plus, check the Cost Plus item parameter (for each item), in the PLU Maintenance program. See the chapter 'PLU Maintenance'.

To flag a *department* for cost plus eligibility, check the Cost Plus department parameter in the Department Maintenance program. See the chapter 'File Maintenance'. With this option enabled, cashiers can sell any item via the department button. Items rung up with this method have cost-plus eligibility.

To access the option, select Cost Plus Programming from the System Parameters menu. The Cost Plus Programming screen displays.

	Up To	Percent
1	10000	20.000
2	5.00	10.000
3	0.00	0.000
4	0.00	0.000
5	0.00	0.000
6	0.00	0.000
7	0.00	0.000
8	0.00	0.000
9	0.00	0.000
10	0.00	0.000

F2] Update

There are 20 ranges (purchase amounts) for which you can define cost plus add-on percentages.

- **To define a range and percentage add-on**
 - 1 Use the *Left arrow* and *Right arrow* keys and *Tab* to position the cursor in the first range (1), in the Upto column.
 - 2 Type in the Up to amount, for example **10.00** and press *Enter*. The cursor moves to the Percent field.
 - 3 Type in the required percentage to add on, for example **20.000**
 - 4 Define all the ranges required.
 - 5 Press *F2* to record the definition.

CDV Programming

The CDV Programming option is used to program customized check digit schemes. Up to 16 CDVs can be programmed. The CDVs can then be used by various functions of ISS45. For example, internal codes can be allocated a CDV scheme in System Parameters.

To access this option, select CDV programming from the System Parameters menu.

Descrip.	Weights	Mod	Rem
1 CD MOD16	654321	11	0
2 7DMOD10	1371371	10	0
3 PLU	371371	0	0
4	0	0	0
5	0	0	0
6	0	0	0
7	0	0	0
8	0	0	0
9	0	0	0
10	0	0	0
11	0	0	0

F2] Update

Adding/updating a new CDV scheme

- **To add/update a CDV scheme**
 - 1 Highlight one of the blank lines, or existing CDV. This line already contains the CDV scheme number. Type in or overwrite the CDV description and press *Enter*.
 - 2 In the Weights field, enter the weighting required for this CDV and press *Enter*.
 - 3 With the cursor in the Mod field, type in the modulus.
 - 4 Last, enter the remainder (if applicable), in the Rem field.
 - 5 Press *F2* to update.

Service Fee Programming

This option lets you charge customers a service fee (commission) for giving them cash back. Use this option to set the fee range.

Service Fee Programming lets you set cash back fees (for check transactions) and to charge customers a fee for performing cash tender-purchase transactions (i.e., giving cash in exchange for a paycheck or when using a debit card).

The fee is based on the cash back amount of a normal sale, or on the purchase amount in a cash tender-purchase transaction.

The fee prints on the customer receipt as a minus value, above the change amount.

Before you define PLU-type service fee ranges, you must define PLUs with suitable descriptions, and the appropriate 'prices' (fees) to charge for each range. For department-type service fees, define a department where service will be allocated.

To access this option, select Check Fee Programming from the System Parameters menu. The Check Fee Programming screen displays.

The only tender number acceptable for service fee programming (on tender-type service fee tables) is tender number 1 (Cash). Do not use tender number 2 (Check) in tender-type service fee tables as problems may occur.

PCM
Ver 7.8.3.0020 TIM'S MARKETS PC# 01 MFS1
Service Fee Programming

Table Number <1-5>... 1

	From Amount	To Amount	Percent	Tender
1	.01	100.00	10.000	1
2	0.00	0.00	0.000	0
3	0.00	0.00	0.000	0
4	0.00	0.00	0.000	0
5	0.00	0.00	0.000	0
6	0.00	0.00	0.000	0
7	0.00	0.00	0.000	0
8	0.00	0.00	0.000	0
9	0.00	0.00	0.000	0
10	0.00	0.00	0.000	0

[F2] Update
[F3] Select Fee type
[F5] Clear Table
[F8] List

Fee Type PLU[] DEPT[] TENDER[]

07/21/2003 11:59:25 Copyright Fujitsu-ICL Inc.

You can define up to five different tables, each containing fee schedules their required cashback or tender value ranges. You can change the default fee type (by Tender Number, by PLU Number, or by Department Number) by pressing the *F3* (Select Fee Type) key.

➤ **To define a table**

- 1 Enter the required table number (1 to 5). In Tender Maintenance, you can link different tables to the required tender type.
- 2 If desired, change the Service Type (by pressing *F3*).
- 3 In each row, enter the required From and To amounts (i.e., the cash back amount for a normal sale or the purchase amount for a cash tender-purchase transaction). Note that the To amount must always be greater than the From amount.
- 4 In each row, enter the appropriate PLU number or Department number to link to each range. To see a list of PLUs or departments, press *F8*.
- 5 For PLU-type service fees, select the required PLU.

Note

You must already have defined PLUs with suitable descriptions, and the appropriate "prices" (fee) to charge for each range.

- 5 When finished, press *F2* to save the table.

System Integrity

System Integrity is intended as a protection against file corruption and to ensure correct prices and other data in the system at all times.

Use this option to define how the System Integrity option must perform. You can also specify which QDX files must pass a checksum process during end of day.

System Integrity also safeguards data when a POS terminal has been working offline (after End of Day has been done), and is then reconnected. The system will then refresh ALL the POS terminal's data files.

To access this option, select System Integrity from the System Parameters menu. The System Integrity menu displays.



Define the following parameters, as required:

Parameter	Description
System Integrity in System	Check the parameter to enable System Integrity. (To allow checksum and data file refresh.)
Data Refresh - PLU FAST Foreground Load Prompt Required	if a cashier prompt is required, check the parameter. A <i>foreground</i> load will occur if the keyboard is not touched for 'n' seconds. (See below). A <i>foreground</i> load is fast, <i>background</i> is slow.
Data Refresh - PLU FAST Foreground Load Protection (zip)	The system will zip the POS terminal's PLU file and start a <i>fast block load</i> . This could take fifteen minutes on 130,000 active PLUs. If loading fails, the zipped file will be reused again.
	Check the parameter if required.
Data Refresh - PLU FAST Foreground Load Prompt Frequency (tickets)	Enter how often the cashier prompt should display, in <i>tickets</i> .
Data Refresh - PLU FAST Foreground Load Prompt Frequency (seconds)	Enter how often the cashier prompt should display, in <i>seconds</i> .

Parameter	Description
Data FAST/SLOW Foreground PLU Load Threshold Percentage	The POS terminal checks active records and compares with the MFS. If a difference of 'n' percentage is found, the PLU file is zipped and a fast block load starts. If a cashier is logged on, a prompt (see parameter number 2 above) recommends to the cashier to perform a fast block load. You can allow the cashier to override this prompt. (See the <i>Bypass</i> parameter below.) Enter the required percentage difference. If the checksum fails, and the difference is less than the percentage you specify, the system will use the slow (foreground) load, and then switch between foreground and background depending on keyboard activity. If the difference is greater than the specified percentage, the fast load will be used.
Data SLOW - PLU Foreground/Background Switch Delay (seconds)	Enter the number of seconds of keyboard activity and inactivity, before a file load switches from foreground to background (and vice versa).
Bypass PLU FAST Foreground message - if Keyboard not Touched (seconds)	Enter the number of seconds of keyboard inactivity, after which the prompt begins to display again.
Delay after File Load (other than PLU) was suspended (seconds)	This parameter relates to the number of seconds to wait before data refresh is resumed (for all files apart from the PLU file) after data refresh is suspended by the cashier.

Press *F2* to update.

QDX Files Checksum Table

Use this table to select the required files for checking, and specify how you want them checked.


Notes

The 'old' checksum parameter in General POST parameters 2 is still available. However, it only checks prices in the PLU file. The new file checksum options described here are more powerful and flexible, allowing you to check up to three fields in the file(s) of your choice.

The system does NOT perform checksum during 24-Hour and Automatic End of Day on POS terminals that have not been logged off.

To check, for example; item prices, PLU code and item description, set the following offsets and lengths for the file PLUPOS.QDX:

- Item price- offset 32, length 4
- PLU code- offset 0, length 7
- Item description- offset 8, length 20



- 1 To select a file, press *F8*. A popup window displays a list of QDX files.
- 2 Highlight the required file and press *Enter* to select it.
- 3 Move the cursor to the Offset (Ofs) field, and enter the required value.
- 4 At the Length (Len) field, enter the required length.


Note

You can check up to three fields in each file.

- 5 (Optional) Enter the maximum records to scan in a relative file.
- 6 Press *F2* to save the setup.

Software Key Information

Software Key Information displays plug serial number and availability of specific optional functionality.

**Poll List Program**

ISS45 contains two alternate computers: a primary computer called the Master File Server 1 (MFS1) and an alternate computer called Master File Server 2 (MFS2). Both computers have identical functionality. POS terminals and workstations update their primary server (either MFS1 or MFS2) with their transaction data and can also access their server files when they require data for activities such as cashier log-on or customer inquiry. The servers update the POS terminals with PLU data.

MFS2 is a backup for MFS1. It automatically receives all transaction updates from MFS1 and automatically updates MFS1. Conversely, MFS1 is a backup for MFS2.

The Poll List Program serves to assign POS terminals to the computers that control these terminals. If a POS terminal is to be used, it must be set up in the poll list.

To access this option, select Poll List Program from the Maintenance & Utilities menu. The Poll List Programming screen displays.

POS No.	Primary	Secondary	In PC
1	0	0	0
2	0	0	0
3	0	0	0
4	0	0	0
5	0	0	0
6	0	0	0
7	0	0	0
8	0	0	0
9	0	0	0
10	0	0	0
11	0	0	0
12	0	0	0

[F2] Update [F10] Print

07/21/2003 15:10:42 Copyright Fujitsu-ICL Inc.

This screen contains four columns:

- The first column lists the numbers of the POS terminals.
- The second column, Primary, serves to enter the number of the PC to which a POS is assigned as the primary computer.
- The third column, Secondary, serves to enter the number of the PC to which a POS is assigned as the secondary computer.
- The fourth column, In PC, serves to enter the number of the PC in which the POS terminal resides, in cases where a PC is used also as a POS terminal (PIP - POS In PC).

Use the *PgUp*, *PgDn*, *Up Arrow* and *Down Arrow* keys to page through the list.

➤ **To assign a POS to PCs**

- 1 Move the cursor to the POS to be assigned.
- 2 In the Primary field, type the number of the PC (1 or 2) which is to serve as the primary computer for this POS.
- 3 Similarly, in the Secondary field, type the number of the PC (1 or 2) which is to serve as the secondary computer for this POS.

Note

If you enter the same number both in Primary and Secondary, the following warning message is issued: Setting the Primary and Secondary to the same value may be invalid.

- 4 Press *F2* to update.
- 5 To assign another POS, repeat steps 1 to 4.

➤ **To print the poll list**


Press *F10*.

Receipt Header/Footer Maintenance

The Receipt Header/Footer Maintenance program serves to design the headers and footers that print on the customer receipt tape. Both the header (top lines of the receipt) and the footer (bottom lines of the receipt) can contain up to 10 lines, and they can be printed in normal or bold characters.

You can link each header/footer to a specific POS.

To access this option, select Receipt Header/Footer Maintenance from the Maintenance & Utilities menu. The Headers/Footers screen displays.



This screen lists the headers and footers that have already been defined. You can page through the list, using the *PgUp*, *PgDn*, *Up Arrow* and *Down Arrow* keys.

Defining a New Header/Footer

- To define a new header/footer
 - 1 Highlight one of the blank lines in the Headers/Footers screen, and select *Update* (press *Enter* or *F2*). A window prompts you for the header/footer name.
 - 2 Type in an appropriate description, and press *Enter*.
 - 3 Press *F2* to continue. The Headers/Footers - Define screen displays.

The left side of the screen contains two windows. The upper window is used for entering the header lines, and the lower window for footer lines.

Defining a header

- 1 The first line of the header window is highlighted. You can enter up to 10 header lines. Use the *Up Arrow*, *Down Arrow* and *Enter* keys to move to the required line.

- 2 Type in the text to be printed on this line of the receipt. You can enter up to 40 characters in normal print. At the end of the line, press *Enter* or the *Down Arrow* to move to the next line.
- 3 Header lines can be printed in bold characters, and they can be centered. After you highlight a line, you can apply one of the functions on the right side of the screen.

➤ **To activate a function**

- Press the *Alt* key and the initialized letter. For example, *Alt+B* for Bold.
- Use the *Tab* key to select the function button and press *Enter* to activate it.


The available functions are:

Function	Description
Bold (Alt+B)	Prints characters in boldface. If you are using this attribute, you can only enter up to 20 characters. After you choose this attribute, the characters are spaced. These lines are marked with the word 'Bold' to the right of the window.
Center (Alt+C)	Centers text. This can be applied to normal or bold text.
Normal (Alt+N)	Returns bold and/or centered text to normal. The text line is marked with the word 'Normal'.
Unprinted (Alt+U)	Clears the line.

Defining a footer

Press *Enter* or *Down Arrow* to continue to the footer window. Follow the instructions in 'Defining a header'.

The following figure illustrates how the screen looks after header and footer lines are entered.



Press *F2* to record the definitions and return to the Headers/Footers screen.

Updating a Header/Footer

- **To update a header/footer**
 - 1 Highlight the required header/footer in the Headers/Footers screen, and select *Update*. The Header/Footer Name window displays. Overtyping a new name, if necessary.
Press *F2* to continue. The Headers/Footers - Update screen displays with the details of the selected header/footer.
 - 2 Follow the instructions in 'Defining a header' and 'Defining a footer', to insert the required changes to the header and footer lines. To change the text on a line, you can:
 - First clear the line using the *Unprinted* (*Alt+U*) function. Then, type in the new text.
 - Overtyping the new text, and use the edit keys to delete or insert characters.
 - 3 Press *F2* to record the changes.

Linking a Header/Footer to POS

After defining a header/footer, you need to link it to the POS terminals where it is printed on customer receipts.

- **To link a header/footer to a POS**
 - 1 Select the *Link POS (Alt+P)* function. The Connect to POS screen displays.
 - 2 This screen lists the POS terminals, and the headers/footer used in each terminal (H/F number and name).
 - 3 Highlight the relevant POS and press *Enter* or *F2*. The Change Header/Footer Number window displays.
 - 4 This window displays the header/footer to which the POS is connected. You can type in the number of another header/footer and press *Enter*. Or, just press *Enter* not to change the current setting.
 - 5 Press *Enter* again or *F2* to update and return to the Connect to POS screen.


Security Maintenance

The Security Maintenance option serves to:

- Assign user IDs, passwords and security levels to ISS45 users.
- Show status and priority of users in the system.
- Define security levels for the ISS45 functions and options.
- Report on user access to menu options.
- Set Closed Circuit TV (CCTV) Parameters

A user must log on to ISS45 with a number and password matching those defined for that user in the security file. A user is authorized to use ISS45 options according to the security level assigned. The user must also have a security level equal to or higher than the security level of the ISS45 function he wishes to perform.

To access this option, select Security Maintenance from the Maintenance & Utilities menu. The Security Maintenance menu displays.



Users Password Definition

The Users Password Definition option serves to assign user IDs, passwords and priorities to ISS45 users, and change their status from Active to Not Active and vice versa. Only active users can access the system.

To access this option, select Users Password Definition from the Security Maintenance menu. The User Password Definition screen displays.

Status	No.	User Name	Password	Priority
Active	1	JIM TURNER	11111	9
Active	2	LESLIE WARNER	00000	9
Active	3	MICHAEL NAUE	12345	9
Active	4	DYLAN WALKER	00000	9
Active	5	SUPERVISOR	00099	9
Not Active	6			
Not Active	7		00000	0
Not Active	8			
Not Active	9			
Active	10	JIM THORNTON	00000	9
Not Active	11			
Not Active	12			
Not Active	13			
Not Active	14			
Not Active	15			
Not Active	16			
Not Active	17			
Not Active	18			

This screen lists the users of the ISS45 system. It shows the following information about each user:

- Status (Active/Not Active)
- No.: (User number)
- User name
- Password
- Priority
- Cashir Link

Adding a New User

- **To add a new user**
 - 1 Highlight one of the blank lines and select *Update*. The Edit User Data window displays.
 - 2 Type in the required user name.
 - 3 In the Active field, press *Space Bar* to make the user active. (Press again to deactivate).
 - 4 In the Password field, enter a password of up to 5 digits. When logging on to the system, the user must enter the assigned password just as it displays here.

- 5 Next, enter a priority from 0 to 9, where 0 is lowest and 9 the highest.
- 6 Every user in the system must have a priority number from 0 to 9. This number is checked against the security level defined for each ISS45 option (see "System Security Levels", later in this chapter). For example, User 1 has priority 5. The security level for End of Day is 9. User 1 cannot, therefore, perform End of Day procedures.
- 7 A user with a security level of 9 can perform all ISS45 functions. With a priority level of 1 - 8, a user can perform only those functions assigned a security level of 1 - 8 or below. A security level of 0 permits a user to use only those functions assigned 0.
- 8 If Control Checks are to be resolved by Front Office users (through the Pocket Office Remote Manager Authorizaton Module), you must associate (link) cashiers with Front Office Users. For the selected Front Office user, choose the cashier user to link to the Front Office user.

Note:

A cashier can only be linked to one Front Office user. Only link those Front Office Users who will be permitted access to the Remote Manager Authorization module.

- 9 Press *Alt+A* to record the definition.

Changing User Status

➤ **To change a user's status from Active to Not Active**

- 1 Highlight the user.
- 2 Select the *Update (Alt+U)* function.
- 3 Move to the Active field and press *Space Bar*.
- 4 Select *Update (Enter)*.

Updating a User

➤ **To update a user's name, password or priority**

- 1 Highlight the user.
- 2 Select the *Update (Alt+U)* function.
- 3 Make the required changes to the relevant fields.

4 Select *Update* (*Enter*).

Printing a Users List

To view or print a list of all ISS45 users, select the *Print* function in the User Password Definition screen.

The list screen displays.

To view all parts of the displayed list use the following:

- *Right Arrow* and *Left Arrow* to shift the screen in the arrow direction.
- *Ctrl+Right Arrow* and *Ctrl+Left Arrow* to shift to the last column and first column.
- *PgUp* and *PgDn* to page through the lines of the list.

Press *F10* to print the list.

Press *F3* or *Esc* to return to the User Password Definition screen.

Users Inquiry

This option allows you to check a user's status and priority.

To access this option, select Users Inquiry from the Security Maintenance menu. The Users list screen displays.

This screen lists the users of the ISS45 system. It shows the following information about each user:

- Status (Active/Not Active)
- No.: (User number)
- User name
- Priority

Scroll through the list with *PgUp*, *PgDn* and *Up Arrow* and *Down Arrow*.

System Security Levels

This option serves to assign a security authorization level (priority) and privilege to each of ISS45's options.

Security authorization levels range from 0 to 9, 0 being the lowest level and 9 the highest. For example, an option with a security level

of 9 can be performed only by a user with a security level (priority) of 9. An option with a security level of 5 can be performed by anyone with priority 5 or higher.

Only users with the correct privilege password can access options that are protected by a privilege.

Setting up Privilege Passwords


Before you set up system security levels, you must set up privilege passwords.

To access the Privilege Setup, exit to DOS. At the DOS prompt in the \PCMASTER directory, type in **ppms/gotoprvg** and press *Enter*. The EPM Privilege Setup screen displays.

- **To assign a password to a privilege**
 - 1 Highlight a privilege level and type in a five character password. As you type, asterisks (*) are displayed. Press *Enter* or *Tab* to continue to the next privilege.
 - 2 Repeat the above step for each privilege, as required.
 - 3 Select *OK* to record the passwords, or *Cancel* to quit without recording.

Assigning System Security Levels

To access the security authorization option, select System Security Levels from the Security Maintenance menu. The Set Menu Priority screen displays.



This screen lists ISS45 options in name sequence.

- **To search for an option**
 - Use the *PgUp*, *PgDn*, *Up Arrow* and *Down Arrow* keys.
 - For faster search, use the *Go To* feature: Start typing an option name. As you enter the letters, they display at the bottom left corner of the list window. The option corresponding to the name you entered is highlighted at the top of the list.
- **To assign a system security level (new or update), to an option**
 - 1 Highlight the option and select *Update*. The *Set Priority* screen for that option displays.
 - 2 This screen lists the sub-options of the selected option. For each of these options, you can enter a priority, a privilege and check or uncheck the *Log* parameter. If you check the *Log* parameter, all user accesses to relevant options are logged. See *User Access Log*, below.

To assign a priority (0-9) to an option, use the *Enter* key to move the cursor to the *Priority* field of that option. Type in the priority.
 - 3 A privilege establishes a higher level of security. Up to 5 privilege levels (1-5) are available. A password is linked to each privilege. When you activate an ISS45 option to which a

privilege level is assigned, you are prompted to enter a password.


- 4 The password you enter must match the password linked to the privilege level. If the password is incorrect, an error message displays: Incorrect Password - Access Denied !!!! Hit any key to continue.
- 5 To assign a privilege level (1-5) to an option, use the *Enter* key to move the cursor to the Privilege field of that option. Type in the privilege level.
- 6 Check the Log parameter to record all user accesses to that option.
- 7 Press *Tab* or *Enter* to select *OK*, or *Cancel* to quit without recording.

User Access Log

This option provides management with a record of user access to options and functions in the ISS45 system. Tracking is maintained for 100 days, including the current day.

ISS45 only logs user accesses if the *Log* parameter in the Set Menu Priority screen is checked, for all options where tracking is required. (See 'Assigning System Security Levels', above).

To access this option, select User Access Log from the Security Maintenance menu. The File selection screen displays.



Select a log file to search from the File Selection screen.

The first file at the top of the list is always the current (today's) transaction file. Note the .QDX file extension.

All the other transaction files listed are zipped (compressed QDX) files. These files are listed in date order, from newest to oldest.

Selecting a File

➤ To select a file

Use the *Up arrow* and *Down arrow* keys to highlight the required file and activate the *Select* (*Alt+S*) function, or press *Enter*. The log Information screen displays.

All accesses to menu options are displayed, showing the following details per record.

- User Number
- User Name
- Description (menu or option name)
- Time

To scroll the list of records, use the *Up arrow*, *Down arrow* and *Page Up/Page Down* keys. The functions available from this screen are

describe below. To move to the functions, use the *Tab* key, or use short cuts (*Alt* key + the highlighted letter) to activate them directly.

By User

- 1 Activate this function, (*Alt+X*) to see all accesses for a specific user number. A pop-up window displays.
- 2 Type in the required user number. All accesses for that user number are displayed.

By Description

- 1 To see all accesses for a specific menu option, select this function (*Alt+X*). A pop-up window displays.
- 2 Type in the required description. Only the first few letters of the menu or option are necessary. For example, "PLU". All accesses with menu options beginning with "PLU" are displayed.

All Records

If you have already selected by user or description, and would now like to see the complete list, select this function. (*Alt+X*).

Print

Use this function (*Alt+X*) to display the report.


To view the complete report, scroll the display with the *Up arrow*, *Down arrow* and *Page Up/Page Down* keys.

Select *Print* (*F10*) to send the report to the printer, or *Cancel* (*F3*) to return to the previous screen.

Record/Playback Keys

This new feature enables you to record key strokes which can be played back at a later stage.

With the Record/Playback keys you are able to print all of the ISS45 screens and reports as hard copy backups.



Example 1

Assume you need to send the exact parameter settings to your dealer for assistance. Instead of manually writing down the settings on paper you can create:

- a hard copy of parameter settings
- a file which contains the screen captures of the different parameter settings

Example 2

You are working with a chain of five stores and you need to get each store's specific parameter settings:

- record the printing process of the necessary parameter screen settings

- send the file (REC-KEYS.DAT) containing the key strokes for printing to the different stores
- each store plays back the recorded key strokes you sent and creates its own report file which can be sent to you

Example 3

You require an hourly printout of certain reports:

- record the printing process of the different reports
- play back the recorded key strokes every hour - this creates a file containing the reports required
- after every playback go to DOS and save the created file to a different name

➤ To Record Keys

- 1 Go to Maintenance and Utilities, Security Maintenance.
- 2 Select Record Keys.
Screen prompts *'Are you sure Yes or No'*.
- 3 Select Yes to start recording key strokes.
- 4 The recording process starts at the Back Office Main Menu screen. A red message at the bottom of the screen indicates that you are now in record mode.
From this point onwards all movements on the Back Office will be recorded until you press *Shift+F3*.
- 5 Go to any menu or screen which you would like to record.
- 6 As you browse through the menus press *Shift+F4* every time you want to print a screen. Use the appropriate print button in each Back Office report you want printed.
- 7 To stop recording press *Shift+F3*.
The key strokes you have recorded are saved in a file called:
REC-KEYS.DAT in C:\PCMASTER

Every time the recording process takes place again, the file REC-KEYS.DAT is overwritten. To prevent the file from being overwritten make sure you rename it.

➤ To Playback Keys

- 1 Go to Maintenance and Utilities, Security Maintenance

2 Select Playback Keys.

The recorded key strokes play back.

Playing back the key strokes creates a file called:

REC-KEYS.RPT in C:\PCMASTER

The REC-KEYS.RPT file contains all printed screens and reports which were recorded. Every time the playback process takes place again, the file REC-KEYS.RPT is overwritten. To prevent the file from being overwritten make sure you rename it.

➤ **To Playback Keys Report**

1 Go to Maintenance and Utilities, Security Maintenance

2 Select Playback Keys Report.

The Playback Keys Report option shows you the contents of the REC-KEYS.RPT file.

The Playback Keys Report contains all the reports and screen captures you recorded.


Note

The playback file is sometimes created on PCs without a printer, therefore, you cannot print during recording or playback. To print the playback file on a PC with a printer, use the *F10* print option in Playback Keys Report.

CCTV Interface

ISS45 interfaces with third-party Closed Circuit TV (CCTV) applications that monitors cashier credibility and helps reduce theft by cashiers at the lanes. WinPOS will gather specific transaction data, convert it to an XML format and transfer it to a third-party database via TCP/IP.

To access this parameters for enabling the interface, select CCTV Parameters from the Security Maintenance menu.



Parameter	Description
CCTV in System	When this parameter is checked, the POS will transmit transaction data via TCP/IP to a third-party CCTV server.
CCTV Server Host Name	This parameter defines the IP address of the CCTV host server.
CCTV Server Port	This parameter defines the port number of the CCTV host server.


Note

The feature is enabled by a bit on the HASP plug. Flag ID #5 is CCTV within the Software Key Information Screen.

LAN Monitoring

The LAN Monitoring option provides an on-line, real time display of the network activities, showing the communication status between the various work stations. Technical personnel can also use the LAN Monitor for debugging.

To access this option, select LAN Monitoring from the Maintenance & Utilities menu. The basic LAN Monitoring screen displays.



The number of PLUs currently in the system displays at the lower left corner of the screen. From the basic LAN Monitoring screen, other monitoring functions are available. They are described below. To exit from the LAN Monitoring screen, press *Esc*.

Freeze

This toggle function freezes the LAN monitoring in the display.

Select this function to freeze the display. The caption on the push button changes to Freeze: ON. Select it again to continue real time monitoring. The button caption returns to Freeze: OFF, the default for this function.

Clear Screen

The Clear Screen function erases all LAN messages in the display, and monitoring continues again.

Active keys

This function displays all the currently loaded QDX files, with the following information for each file:

- File number
- Path and file name
- File size

The Active Keys list is scrollable. Use the *up arrow*, *down arrow*, and *Page Up*, *Page Down* keys to scroll the list. To print out the Active Keys list, select *Print*, or to return to the LAN Monitoring screen, select *Exit*.

Debug

This toggle function displays LAN messages in hex and text format, making it easier for technical personnel to see what's happening in the system.


Select this function to display messages in HEX. The caption on the push button changes to Debug: ON. Select it again to display messages in text format. The button caption returns to Debug: OFF, the default for this function.

Watch File

This function displays communication messages similar to those you see in the basic LAN monitoring screen, but also displays the date and time of each message. In addition, you can also scroll backward and forward through the messages.

The Active Keys list is scrollable. Use the *Up Arrow*, *Down Arrow*, and *Page Up*, *Page Down* keys to scroll the list. To print out the Active Keys list, select *Print*, or to return to the LAN Monitoring screen, select *Exit*.

LAN Comm



Use this function to see the communication status of all the POS terminals to servers (MFSs). This option can show you at a glance, terminals that are not online. The screen is divided into two halves. The left half lists all POS terminals that could be polled by PC number 1 (MFS1). A red block highlights all terminals currently online to the PC. The right half contains a similar list of POS terminals polled by PC number 2 (MFS2). If your store configuration has only MFS1, the right hand list is grayed out.

To return to the LAN Monitoring screen, select *Exit*. Press *Esc* to exit to the Maintenance & Utilities menu.


Date and Time

The Date and Time option is used to change the date and time in POS terminals and the computers (MFSs). Use this option to change the current working date when Automatic End of Day is active.

Note

The first time you set up Automatic End of Day, you have to reset the current working date. The next working date (in the grayed out field) is automatically calculated. After you've set the End of Day parameters, check the date here and change it if required.

When you change the date and time through this function, the system automatically changes the date and time in all POS terminals and other PCs in the back office. To access this option, select Date and Time from the Maintenance & Utilities menu. If Automatic End of Day is active, the Date & Time screen displays its Automatic End of Day settings.




The current system date displays in the System Date field. Press *Enter* to retain this date or overwrite a new date and press *Enter*. The System Time field displays the system time. Press *Enter* to retain this time or overwrite a new time, and press *Enter*. If you run Automatic End of Day in your store, reset the current working date if required. The Next Working Date field is grayed out and cannot be accessed. However, when you reset the Current working date, the Next Working Date is automatically incremented by 1.

Press *Enter* or *F2* to update the terminals with the new dates and time, or *Esc* to quit without updating.

CCMS LOG

This option provides a log report of CCMS messages sent and received from the CCMS (Club Card Maintenance Server).


Log is provided only if your system works with CCMS server connection.



Field Engineer's Utilities

The Field Engineer's Utilities option provides access to various utilities to be used by authorized field engineers.

To access this option, select Field Engineer's Utilities from the Maintenance & Utilities menu. The Field Engineer's Utilities menu displays.



QuickDex Definition

This option serves to define and update QuickDex files and QuickDex general parameters.

The QuickDex file server does not use normal DOS calls and therefore reduces disk access time and memory requirements. Memory above 1MB can be used for QuickDex memory files.

File size is determined by the length of the record and the number of records. Multiply the record length and the number of records to determine the initial allocated size of the file. A file can be extended by increasing the maximum number of records. A reduction in file size results in an illegal QuickDex file. Any change to QuickDex parameters must be followed by rebooting both PCs in order to update the changes.


Up to 250 QuickDex files can be defined.

To access this option select QuickDex Definition from the Setup Parameters menu. The QDX/DRVfile menu displays.




Define QuickDex Files

To define or update QuickDex files select Define QDX Files (F1) from the QDX/Drvfile menu. The QDX Files screen displays.



This screen lists the QuickDex files defined in the system, showing the path, name and description of each file.

- **To search for a file**
- Use the *PgUp*, *PgDn*, *Up Arrow* and *Down Arrow* keys.
 - For fast search, use the *froM* function: Select *froM* (*Alt+M*). A search window displays.



Type in the number of the file you want to locate and press *Enter* twice. The required file displays at the top of the screen.

Defining a QuickDex File

To define a QuickDex file, highlight one of the blank lines in the QDX Files screen, where the message 'file not defined.....' displays. The QuickDex File Parameters screen displays.

PCM

Qdex files setup File name : Q-DEX.PRM File # 63

Remark :
 QDEX file name :
 File type : Index [↓] [] Wrap around
 QDEX record size : 0
 Key length : 0
 Key offset in record : 0
 QDX flag offset : 0
 Maximum records : -1
 Block size : Auto [↓]
 Split percent : - 0 - [↓]
 Relative linked file : 9999
 [] Guaranteed WRITE
 [] Fill file with ZERO when created (Similar to q-empty /z??)
 DRUFILE entry number : 0
 [] Write local, [] Mask backup, read 0, Write 0, Backup 0
 [] Use SUPER INDEX for this file
 Super index file # : 255 Name :
 Update eXit Output file Redirection table QDX files

Fill in the parameters as explained in the following table.

Field	Description
Remark	Enter any remark or description in this field. Remarks have no effect on the execution of QuickDex files.
QDEX File Name	Path name and file name.
File Type	Specify the file type for this file. To accept the default Index, press <i>Enter</i> . To select another type, press the <i>Right Arrow</i> . A drop-down list opens. Highlight the required option, and press <i>Enter</i> . The possible types are: - Index - Relative - FIFO - Relative Expansion - Super Index
Wrap Around	This defines a cyclical file for FIFO files only. Check this parameter (by pressing the <i>Space Bar</i>) to prompt when the file is full, leave blank to continuously loop file.
QDEX Record Size	Number of bytes per record. Mandatory.
Key Length	Length of the record key, in bytes.

Field	Description
Key Offset in Record	Starting location of the key in the record (starting from 0).
QuickDex Flag Offset	Location of the QuickDex reserved flag (1 byte). The flag can be located anywhere in the record.
Maximum Records	Mandatory. Depends upon user requirements.
Block Size	Block size in bytes. Select a size from the drop-down list (multiples of 512). To accept the default Auto (automatic allocation), press <i>Enter</i> .
Split Percent	Determines what percentage of block space is used before a block is split. Select a percentage from the drop-down list.
Relative Linked File	File number of the file containing information about the PLU file.
Guaranteed WRITE	Flush every write command to the disk (slow but secure option).
DRVfile Entry Number	Routing information.
Use Super Index for This File	Check this parameter if a super index containing pointers to QuickDex indexes should be used for this file. Then enter the number of this file and its path and name.


Select *Update* (*Alt+U*) to record the definition.

Other Functions

Output File

This function allows you to export a QuickDex file. It builds a file named Q-SETUP.OUT containing the specified QuickDex file. This file can be merged to another QuickDex file, in any other system.

Select the *Output file* function (*Alt+O*). The following window displays.




To append this QuickDex file to an existing output file, select *Append*. To create a new output file, select *New File*. This deletes an existing output file.

Redirection Table


This function displays the DRVFILE redirection table.

Select the *Redirection table* function (*Alt+R*). The following window displays.



QDX Files

This function displays a list of the QuickDex files in the system. Select the *QDX files* function (*Alt+Q*). The following window displays.



You can page through this list, using the *PgUp*, *PgDn*, *Up Arrow* and *Down Arrow* keys.

Updating a QuickDex File.

To update a QuickDex file, highlight the file in the QDX Files screen and select *Update*. Follow the instructions in 'Defining a QuickDex File'.

Deleting a QuickDex File

- 1 To delete a QuickDex file, highlight the required file in the QDX Files screen.
- 2 In the confirmation box, select *Update* to delete.

Printing a List of QuickDex Files


To print a list of the QuickDex files, select *Print* in the QDX Files screen.

Define QuickDex General Parameters

This option serves to set a number of general parameters for QuickDex.

DRVPOS is the device driver interface between the software application and the resident drivers. Each resident driver has an entry number to DRVPOS where the location of the driver is defined. DRVPOS eliminates the use of many software interrupts.

To access the general parameters option, select General Parameters (*F2*) from the QDX/Drvfile menu. The QDX General Parameters screen displays.



Fill in the parameters as explained in the following table.

Field	Description
DRVPOS Entry	This field displays the value 5 and may not be changed.
Maximum Number of Files	Maximum number of QuickDex files the file server can handle.
Relative Files Super Index Path	Path to the super indexes.
Fast Load Path	Path to the load indexes (containing QuickDex pointers for files).

Convert 7.X Files to 7.3 Files


This option serves to upgrade version 7.1 and 7.2 files to version 7.3 files.

Use this option after installing an *upgrade*.

Note

This option is for Field Engineer use only.

To access the option, select Convert 7.X Files to 7.3 Files, from the Field Engineer's Utilities menu. Enter the Field Engineer password. A warning message displays.



Warning

Once you start this process you cannot stop it. If you are sure you want to convert files, press *Enter* to continue, or *Esc* to exit.


Build PLU File from Comm. File

The Build PLU File from Comm. File option serves to add item records created at another location to the PLU file, without having to enter the PLU data manually.

To access this option, select Build PLU File from Comm. File from the Field Engineer's Utilities menu.

You are prompted to confirm the operation. Select *Yes* to continue, or *No* to return to the menu.

The program screen displays.



Enter the path and the name of the source file. The path name of the previously converted file displays by default. The destination file path and name are displayed automatically.

If the path is valid and the specified file is a comm file, it is converted without additional user intervention. The number of records converted is displayed in the Source Record Length field.


Compare and Rebuild Mix & Match File

This option scans the main PLU file and builds a Mix & Match index.

To access the option, select Compare and Rebuild Mix & Match File, from the Field Engineer's Utilities menu.

You are prompted to confirm the operation. Select *Yes* to continue, or *No* to return to the menu.

The process starts and a window displays showing the records being built during the process.




Compare and Rebuild POST PLU File

This option checks and compares the main PLU file against the POST PLU file. If the number of items in the two files does not match, this program builds a new POST PLU item file, based on the main PLU file.

To access the option, select Compare and Rebuild POST PLU File, from the Field Engineer's Utilities menu.

You are prompted to confirm the operation. Select *Yes* to continue, or *No* to return to the menu.

The process starts and a window displays showing the records being built during the process.



Build Audit Seq File

ISS45 includes a PLU Maintenance Audit feature which serves to record all the operations performed in the PLU file (new items, updates, price changes, etc.) in an audit log file. To use this feature, the system parameter 'PLU Maintenance Audit' (see 'System Parameters', earlier in this chapter) must be checked.

The Build Audit Seq. File option converts a QuickDex audit file to a sequential file, for backward compatibility. Older versions of ISS45 use sequential audit log files.

To access the option, select Build Audit Seq File, from the Field Engineer's Utilities menu.

You are prompted to confirm the operation.

Select Yes to build a sequential audit file, or No to return to the menu.

Unzip PLU File

The Unzip PLU option will unzip an ISS45 version 8 PLU file, convert it to QDX and overwrite your current PLU file. To access this option, select Unzip PLU files from the Field Engineer's Utilities menu.

Place the zip file in the \PCMASTER\TMP folder (and name it MSTRFILE.ZIP) before performing this function.

POS Keyboard Programming

The POS Keyboard Programming option enables you to customize the keyboards of the POS terminals.

To access this option, select POS Keyboard Programming from the Maintenance & Utilities menu. The POS keyboard menu displays.


Use the options on this menu, as follows:

- **Function Maintenance.** This option lists all the functions available on a POS terminal. A function name can be changed or a new function can be added by an authorized user.
- **Program Keys.** This option is used to define a keyboard layout by assigning POS functions to keyboard keys, and defining preset keys. Different POS terminals may utilize different keyboards, so there may be several layouts available.
- **Link POS to Keyboard.** After designing a keyboard layout for a POS terminal, it must be linked to that terminal via the link POS to keyboard option (or the POST Configuration option).

Function Maintenance

The Function Maintenance option lists all the functions available on a POS terminal, and allows you to change a function name and add new functions. These operations are performed by authorized personnel only.

To access this option, select Function Maintenance from the POS Keyboard menu. The Keyboard Functions screen displays.




This screen lists the functions available on POS terminals.

- **To search for a function**
 - Use the *PgUp*, *PgDn*, *Up Arrow* and *Down Arrow* keys.
 - For faster search, use the Go To feature: Start typing a function number. As you enter the digits, they display at the bottom left corner of the list window. The function corresponding to the number you entered is highlighted at the top of the list.

Adding a New Function

- **To define a new function**
 - 1 Select *Insert*. The Keyboard Function Maintenance screen displays.



- 2 Type in the Function Number. You use this number to refer to a function throughout the system. The function number must be unique. Press *Enter*.
- 3 Enter the name of the function.
- 4 Press *F2* to record the definition.

Other Functions

In this screen, you can use the same functions as those described in 'Updating a Function'.

Updating a Function

This function allows you to update the name of a function.

- 1 Highlight the required function in the Keyboard Function Maintenance screen, and select *Update*. The update screen displays.
 - 2 To enter updated data in a field, move the cursor to that field using the *Enter* or *Tab* key. Type or overwrite the new data. Follow the instructions in "Adding a New Function".
 - 3 Press *F2* to record the changes.
- **To display another function**
- Type in the function number and press *Enter*; or

- Press *F8* to open the functions list window. Locate the required function using the *PgUp*, *PgDn*, *Up Arrow* and *Down Arrow* keys. Press *Enter* to display it.


➤ **To page through functions**

Press *F10* to display the next function. Press *F9* to display the previous function.

Program Keys

This option serves to define a keyboard layout. Keyboard layouts can be defined for specific POS terminals as well as for different *types* of keyboard.

To access this option, select Program Keys from the POS Keyboard menu. The Keyboard Selection screen displays.



This screen displays the keyboard layouts defined in the system.


Defining a New Keyboard Layout

Note


A new keyboard layout can also be defined using the Copy function, and then redefining that layout. (see 'Copying a Keyboard Layout', later in this chapter).

➤ **To define a new keyboard layout**

- 1 Highlight one of the blank lines in the Keyboard Selection screen, and select *Update*.
- 2 Select the *Update Name* function (*Alt+N*) to assign a name. The Keyboard Name window displays.
- 3 Type in the name and press *F2*. The name now appears on the keyboard selection list.
- 4 Select the *Update* (*Alt+U*) function. The Keyboard Data screen displays.




- 5 This screen lists the functions that you assign to the keyboard keys. At this stage, the screen is empty.
- 6 To assign a function, select *Insert* (*Alt+I*). The Keyboard Keys - Update screen displays.



- 7 On the keyboard, press the function key to be programmed. For example, the Enter key. The name of the key displays in the Key Name field. The cursor is now positioned on Keyboard sale mode.
- 8 A keyboard key can be programmed to activate different functions in Sale Mode and Tender Mode. In the Keyboard sale mode field, specify the required function for Sale Mode. There are two options:
 - A *general* function from the standard functions defined in the system (see 'Function Maintenance', earlier in this chapter).
 - A *preset* function such as a PLU item, a department, a return, etc.

General Function

To assign a general function, select the *General* function (Alt+G). The Keyboard Function window displays.



Use the *PgUp*, *PgDn*, *Up Arrow* and *Down Arrow* keys to locate the required key, and press *Enter* to select it.

The function number and name appear in the Keyboard sale mode and Function Name fields.

Press *Enter* to continue to Keyboard tender mode. To assign a function for Tender Mode, repeat the same procedure as for Sale Mode. If no Tender Mode definition is needed, just press *Enter* to continue.


Note:

The Price Shift 1, Price Shift 2 and Price Shift 3 keyboard functions (numbers 1041, 1042 and 1043 respectively) allow a different price to be charged for an item by calling a designated PLU associated with the price shift key. This feature allows a store, for example, to charge a different price for an item that is one-day old, two-days old or is out-of-date. The item file will need to be maintained according to the following rules.

Each Price Shift key, when depressed prior to scanning or key-entering the PLU number will append a single digit to the PLU number according to the Price Shift key (1, 2 or 3) and retrieve the information from the generated PLU number. For example, using Price Shift 1 prior to entering PLU "50", will ring PLU "501". Using Price Shift 2 prior to entering PLU "50" will ring PLU "502". Finally, using Price Shift 3 prior to entering PLU "50" will ring PLU "503".

Preset Function

To assign a preset function, select the *Preset* function (*Alt+P*). The Keyboard Preset Functions window displays.



Press the *Right Arrow* to select a code. A drop-down window lists the available options:

- Undefined
- PLU
- Department
- Tender
- Discount
- Return
- Expenses (payouts and receipts)

Highlight the required operation code and press *Enter* to select it.

Press *Enter* to continue. A window prompts you for specific information depending on the operation code you selected.

For PLU

The Preset Key to PLU window displays.

Enter the number of the PLU item to be rung up by the key you are defining. You can select an item from the items list window, by pressing *F8*.

For Department

The Preset Key to Department displays.

Enter the number of the Department to be rung up by the key you are defining. You can select a department from the departments list window, by pressing *F8*.

In the Value field, enter the value to be automatically entered by the key. Press *Enter* to continue.

For Tender

The Preset Key to Tender window displays. This window is similar to the Preset Key to Department window.

Specify the Tender Number and the Value to be entered by the key.

For Discount

The Preset Key to Discount window displays. Specify the number of the discount to be performed by the key you are defining.

For Return

The Preset Key to Return window displays. Specify the number of the return to be performed by the key you are defining.

For Expense

The Preset Key to Expense window displays. Specify the payout/receipt code to be entered by the key you are defining.

- 1 After selecting the operation code and entering its details, press *F2* to record the preset function. The Keyboard Keys Update screen returns with the Function Name, Preset Opcode, Preset Number (PLU number, department number, etc.), and the Preset name (PLU item name, department name, etc.). The cursor appears at the Alphanumeric state field.

ISS45 PCM Keyboard Keys Update

Keyboard.....ISS45 KEYBOARD
Key name.....[p]

Keyboard sale mode.....8026
Function name.....PRESET
Preset opcode.....PLU
Preset number.....000000004027
Preset name.....IDAHO POTATOES

Keyboard tender mode.....0000
Function name.....Not Defined
Preset opcode.....
Preset number.....
Preset name.....

Alphanumeric state.....0
Alphanumeric name.....Not Defined

Keyboard privilege.....0
Keyboard keylock.....0

Press general function or preset key.

General
Preset
Clear
Set Key
[F2] Update

- 2 Press *Enter* to skip this field and continue to the Keyboard privilege field.
- 3 To assign a keyboard privilege to the key, type in the required value. Valid privileges are 1-8, with 8 being the highest privilege. Use keyboard privileges to ensure that certain functions are activated only by authorized employees, for example, supervisors.
- 4 If necessary, a keyboard keylock position may be defined. Type in the required value. Valid keylock positions are 1 - 8. The actual range on the standard keyboard is 1 - 5.

Keylock positions are used to impose control by supervisors and management.

Note

Keylock position numbers are dependent on the keyboard type connected to the POS terminal.

- 5 Having assigned a function to a key, press *F2* to record the definition.
- 6 To quit, press *Esc*.

The Keyboard Data screen now lists the functions and preset operations you have assigned to keyboard keys.

From this screen you can update or delete a key assignment. This is explained in 'Updating a Keyboard Layout', below.

Updating a Keyboard Layout

➤ To update a keyboard layout

- 1 In the Keyboard Selection screen, highlight the required keyboard, and select *Update*. The Keyboard Data screen displays.
- 2 Perform the required function:

Function	Description
Insert	Select <i>Insert</i> to enter a new assignment. Follow the instructions in "Defining a New Keyboard Layout".
Update	Highlight a key assignment and select <i>Update</i> (<i>Alt+U</i>). The Keyboard Keys - Update screen displays the details of the assignment. The cursor is positioned on Keyboard sale mode. Select the function from the list window. To select a general function, press <i>Alt+G</i>. The Keyboard Functions window displays. The Used column in this window shows the number of times each function has been used (a √ sign for each use). To select a preset function, press <i>Alt+P</i>. Change the Keyboard tender mode in the same way, if necessary. Press <i>F2</i> to update.
Delete	Highlight the key assignment to be deleted, and select <i>deLete</i> (<i>Alt+L</i>). In the confirmation box, select <i>Yes</i> to delete or <i>No</i> to retain the key assignment.

➤ To update a keyboard name


- 1 In the Keyboard Selection screen, highlight the required keyboard, and select *Update Name* (*Alt+N*). The Keyboard Name window displays with the name of the selected keyboard.
- 2 Overtyping a new name.
- 3 Press *F2* to update.

Copying a Keyboard Layout

You can create a new keyboard layout based on an existing layout. First copy the layout and then make the necessary changes via the *Update* function.

➤ **To copy a layout**

- 1 In the Keyboard Selection screen, highlight the keyboard from which you want to copy, and select the *coPy* (*Alt+P*) function. The Keyboard Copy window displays.



- 2 Type in the number of the new keyboard layout. Press *Enter* and then *OK* (or *Enter*). The copied layout appears in the list.

Note

If the target keyboard already exists, a message box displays the following: Keyboard exists. Are you sure? Select *No* if you don't want to copy onto the existing keyboard. Select *Yes* to override the existing keyboard.

Deleting a Keyboard Layout

➤ **To delete a keyboard layout**

- 1 In the Keyboard Selection screen, highlight the required keyboard, and select *deLete* (*Alt+L*).
- 2 In the confirmation box, select *Yes* to delete or *No* to retain the layout.

Printing a Keyboard Report

➤ To print a keyboard report

In the Keyboard Selection screen, highlight the required keyboard, and select *Report* (*Alt+R*). The Keyboard Report Selection window displays.

Two type of reports can be viewed and printed.

Function Usage Report

Select the *Func Usage* function (*Alt+F*). The report screen displays.

This report lists functions in function number sequence, and shows which keys are assigned to each of these functions.

To view all parts of the displayed list use the following:

- *Right Arrow* and *Left Arrow* to shift the screen in the arrow direction.
- *Ctrl+Right Arrow* and *Ctrl+Left Arrow* to shift to the last column and first column.
- *PgUp* and *PgDn* to page through the lines of the list.

Press *F10* to print the list.

Keys Defined

Select the *Keys Defined* (*Alt+K*) function. The report screen displays.

This report lists key assignments by keys.

For functions available on this screen, refer to 'Function Usage Report', above.


Link POS to Keyboard

After defining a keyboard layout, you need to link it to the POS terminals where it is used, via the Link POS to Keyboard option.

Note

A keyboard can be linked to a POS terminal also via the POST Configuration option (see 'POST Configuration', earlier in this manual).

To access this option, select Link POS to Keyboard from the POS Keyboard menu. The POS Keyboard Link screen displays.




POS No.	Keyboard Number	Keyboard Name
1	2	ISS45 LAB1 92R
2	2	ISS45 LAB1 92R
3	2	ISS45 LAB1 92R
4	2	ISS45 LAB1 92R
5	2	ISS45 LAB1 92R
6	2	ISS45 LAB1 92R
7	2	ISS45 LAB1 92R
8	2	ISS45 LAB1 92R
9	2	ISS45 LAB1 92R
10	3	SNIKEY KEYBOARD
11	2	ISS45 LAB1 92R
12	2	ISS45 LAB1 92R
13	2	ISS45 LAB1 92R
14	2	ISS45 LAB1 92R
15	3	SNIKEY KEYBOARD
16	2	ISS45 LAB1 92R
17	2	ISS45 LAB1 92R
18	1	ISS45 KEYBOARD

This screen lists the POS terminals. If a keyboard has been linked to a POS, the keyboard number and name are also displayed.

➤ **To link a keyboard to a POS**

- 1 Highlight the POS and select *Update* (press *Enter*). The POS Keyboard Link window displays.



POS Keyboard Link

POS number.....▶ 1

Keyboard number.....▶ 2

[F2] Update [F8] List [F9] Prev [F10] Next

- 2 The selected POS number displays. If you want to link another POS, type in the POS number, or use the *F9* (Previous) and *F10* (Next) keys to display a POS.
- 3 Press *Enter* to continue to the Keyboard Number field. Specify the number of the keyboard layout to be linked: type in the keyboard number, or press *F8* to select one from the Keyboards List window.
- 4 Press *F2* to update the definition.

Electronic Journal

Use this option to view cashier transactions and reports, for the current day or for previous dates. Transaction information is picked up from the daily transaction files.

To access this option, select Electronic Journal from the Maintenance & Utilities menu.

For more information, see the 'Electronic Journal User's Guide'.

Electronic Journal - Search Facility

A search facility 'Supervisor' (option 19) has been added to the Electronic Journal. This option allows users to search for any supervisor overrides.

Electronic Journal - Supervisor Authorizations

Transactions which needed supervisor authorization at the PoS terminal will appear in the Electronic Journal. The word 'Supervisor' and the supervisors password will be shown.

POST Graphics

Two options are available from this menu:

- Graphic Logo Maintenance - for receipts
- Screen Saver Setup - POS terminal screen savers

Graphic Logo Maintenance


You can use this utility to maintain up to 5 predefined graphic logos. Only .bmp (bitmap) graphic files may be used, and they must reside in the C:\PCMASTER\SEQ directory. You must set logo dimensions in a suitable graphics or paint program. Make sure the logo size meets the following requirements for each printer type:

Printer Type	BMP File Size
Epson TM930	Width - 180 pixels maximum. Height - No limit.
Epson TMT80 (Thermal)	Width - 192 pixels maximum. Height - No limit.
Axiohm 7156 (Thermal)	Width - 448 pixels maximum Height - 384 pixels maximum
Note Although the dimensions above are the maximum allowed, you cannot use both at the maximum size. For example; if width is 448, height must be <i>less</i> than 384. The maximum size must be equal to or less than width x height, with a maximum of 172032. The logo image is loaded into printer memory when the POS terminal is powered up. This allows high speed printing of the logo.	
Fujitsu	Width - 400 pixels. Height - 48 pixels. The logo is loaded into printer memory.


Notes

You must use pixels (PELS) for defining logo dimensions. Save the logo with black and white settings, NOT color.

- **To access Graphic Logo Maintenance**
 - 1 From System Maintenance and Utilities select POST Graphics. The POST Graphics sub-menu displays.



- 2 Select Graphic Logo Maintenance. The Graphic Logo Maintenance screen displays.



The screen lists the logo numbers and names (if any), or if none, the message Not Defined.

The right side of the screen contains function buttons. Each button activates a function such as updating, deleting or naming a logo.

- **To select a graphic logo**
 - 1 Highlight the logo required (or line number if not defined), and select *Update* (press *Enter*). The Select a file window displays.
 - 2 Move the cursor to highlight the required file and press *Enter* to select it.
 - 3 A dialog box displays with the file name selected. You can change the name here if desired. Type in the new name and select *Continue* (press *Enter*).
- **To delete a graphic logo**
 - 1 Move the cursor to highlight the file for deletion and select *deLete* (*Alt+L*).
 - 2 In the confirmation box select *Yes* to delete the logo, or *No* to leave it.
- **To rename a graphic logo**
 - 1 Move the cursor to highlight the required file and select *Name* (*Alt+N*).
 - 2 A dialog box displays with the file name selected. Type in a new name and select *Continue* (press *Enter*) to rename the file, or press *Esc* to leave the name unchanged.

Screen Saver Setup

When the POS terminal is in signed-off mode, up to ten different graphic images can be displayed. You can set different display times (delays) for each image.

The Screen Saver Setup lets you specify the sequence and display time of each image.

This feature supports only .bmp images, which must reside in the directory C:\PCMASTER\SEQ


Note

Image size, in pixels: Minimum: 320 x 200. Maximum: 640 x 480

- 1 Exit to DOS and go to the directory C:\PCMASTER\SEQ
- 2 Copy the appropriate .bmp files from your diskette to this directory.

➤ **To Access Screen Saver Setup**

- 1 From System Maintenance and Utilities select POST Graphics. The POST Graphics sub-menu displays.
- 2 Select Screen Saver Setup. The Screen Saver Setup screen displays.



This screen lists all the entries for screen savers (1-10) defined in the system, showing the following information per entry:

- Number
- Screen Saver Name
- Delay: The display time for the image at the POS terminal.

➤ **To add a new screen saver**

- 1 In the Screen Saver Setup screen, select Update. A list of images displays.
- 2 Select the required image. Use the *PgUp*, *PgDn*, *Up Arrow* and *Down Arrow* keys. The details screen displays.
- 3 Edit the name if required. This does not change the original filename.
- 4 Enter the number of seconds to display the image.

- 5 Select *Continue*. The entry now shows the information you entered.

➤ **To update the image details**

- 1 Highlight the required entry in the Screen Saver Setup screen and select *Details*. The details screen displays.
- 2 Edit the name if required. This does not change the original filename.
- 3 Change the delay as required.
- 4 Select *Continue*.

➤ **To delete an image**

- 1 Highlight the required entry in the Screen Saver Setup screen and select *DeLete*.
- 2 Select *Yes* to delete. The entry displays as 'not defined'.
- 3 To update the POS terminal, you must select '*Load All*'.

➤ **To load delays to the POS terminal**

- 1 Select *Load Delay*.
- 2 Select *Yes* to confirm the load.

➤ **To load an image to the POS terminal**

- 1 Highlight the required entry.
- 2 Select *Load Image*.
- 3 Select *Yes* to confirm the load.

➤ **To load images and delays to the POS terminal**

- 1 Select *Load All*.
- 2 Select *Yes* to confirm the load.

Note

The process of loading images or image details to the POS terminals could take a few minutes (dependent on the number and size of images). During loading, the POS terminals can NOT be used.

While the POS terminal is in signed-off mode, the images display according to the sequence you set up. Each image displays for the number of seconds defined.

- Press the *Sign-on* key to cancel the screen saver display.

- When the POS terminal is once again in signed-off mode, the next image in the sequence displays

Note

The images file (number 88) is not loaded during a cold start. After a cold start is performed, you must reload the images to the POS terminal.

System Alerts

System alerts notify office staff or management of technical problems, security violations, and other out-of-line or exception situations on the POS terminals.

When a specified POS terminal *activity* or *event* activates an alert, a red ALERT indicator displays on the lower part of the PC (workstation/MFS) screen. Depending on how alerts parameters are set, the ALERT indicator could soon be followed by a pop-up message. This message displays the reason for the alert. See example illustrated below.

The Alert message includes:

- POS terminal number
- Time occurred
- Queued alerts (number of alerts generated and still to display)

Select *Continue* to close the Alert pop-up. If there are other queued alerts, they pop-up in their sequence of occurrence. The pop-up may display again after 'n' minutes, depending on how its been defined.

The System Alerts option allows you to:


- Report on all alerts—current day plus history
- Insert, update, and delete system alerts
- Set alert parameters

Some examples of alert types:

- Printer Error
- Scanner Error
- Drawer Full

- Password Violation
- POS Off-line

To access the System Alerts option, select System Alerts from the Maintenance & Utilities menu. The System Alerts menu displays.




Each option on this menu leads to another option, containing reports, maintenance screens and parameters.

Alerts Log

This option provides management with a record of all alerts generated in the ISS45 system.

ISS45 does not log alerts if the Ignore this alert parameter is checked. See Alert Types Maintenance, below.

To access this option, select Alerts Log from the System Alerts menu. The File Selection screen displays.



The first file at the top of the list is always the current transaction file. Note the .QDX file extension.

All the other transaction files listed are zipped (compressed) QDX files. These files are listed in date order, from newest to oldest.

Selecting a File

➤ To select a file

Use the *Up arrow* and *Down arrow* keys to highlight the required file and activate the *Select* (*Alt+S*) function, or press *Enter*. The Alerts List screen displays.

All logged alerts are displayed, showing the following details per record.

- POS/PC Number
- Type (alert number)
- Description (alert message)
- Time occurred

To scroll the list of records, use the *Up arrow*, *Down arrow* and *Page Up/Page Down* keys. The functions available from this screen are

described below. To move to the functions, use the *Tab* key, or use short cuts (*Alt* key + the highlighted letter) to activate them directly.

Searching for Alerts

Select the *Search by* option to see the available choices.

By Opcode (type)

- 1 Activate this function, (*Alt+O*) to see all alerts for a specific opcode number. A pop-up window displays.
- 2 Type in the required opcode number. All alerts for that opcode number are displayed.

By POS

- 1 To see all alerts for a specific POS terminal, select this function (*Alt+P*). A pop-up window displays.
- 2 Type in the required POS number. All alerts for that POS display.

By PC

- 1 To see all alerts for a specific PC or workstation, select this function (*Alt+C*). A pop-up window displays.
- 2 Type in the required PC number. All alerts for that PC display.

By Time

- 1 To see all alerts for a specific time, select this function (*Alt+T*). A pop-up window displays.
- 2 Type in the required time. All alerts for that time display.

Sorting

For ease of use, the listed alerts can be sorted in three different ways.

- By Opcode
- By POS
- By Time

To activate sort options, select *Set Sort*. The Sorting Criteria window pops up. Activate the sort function as in Searching, above.

Display all Records

If you have searched for a small range of information, for example all alerts from 14:00 to 14:30, use this option to re-display all records.

Printing

Use this function (*Alt+P*) to display the report.


To view the complete report, scroll the display with the *Up arrow*, *Down arrow* and *Page Up/Page Down* keys.

Select *Print (F10)* to send the report to the printer, or *Cancel (F3)* to return to the previous screen.

Alert Types Maintenance

This option is used to define alerts and their behavior. ISS45 is already configured with numerous alerts. To insert a new alert, the required function (program) must be developed first.

To access the Alert Types Maintenance option, select Alert Types Maintenance from the System Alerts menu. The Alert Types Maintenance screen displays.



The screen lists all the alerts in the Alerts file, showing the alert number and message for each alert.

➤ **To search for an alert**

- Use the *PgUp*, *PgDn*, *Up Arrow* and *Down Arrow* keys.
- For faster search, use the Go To feature: Start typing an alert number. As you enter the digits, they display at the bottom left corner of the list window. The alert record corresponding to the number you entered is highlighted at the top of the list. For example, as you type 204, the system first highlights alert 2, then alert 20, and then alert 204. If the number you entered does not exist, the next alert is highlighted.

The right side of the screen contains function buttons. Each of these buttons activates a function such as updating alert information or adding a new alert. These functions are described later in this chapter.

➤ **To activate a function**

- 1 If the function applies to a specific alert (e.g. Update an existing alert), highlight that alert. If not (e.g. Insert a new alert), just perform step 2.
- 2 Do one of the following:

- Press the *Alt* key and the initialized letter. For example, *Alt+U* for Update.
- Use the *Tab* key to select the function button and press *Enter* to activate it.

Adding a New Alert

This function enables you to add new alerts to the alerts file. A new alert needs to be defined, for example, when a new event on the POS terminal is created, and you need to report on all occurrences of the event.

- 1 In the Alert Types Maintenance screen, select *Insert*. The Alert - Insert screen displays.

PCM
Ver 7.0.9.1004 TIM'S MARKETS PC# 01 MFS1

Alerts Maintenance

Number.....>> 99
 Message.....> CCMS offline
 Timeout between confirmation and re-alert...> 0
 Pop-Up alert.....> [N]
 Pop-Up message.....> [N]
 Password required on confirmation.....> []
 Ignore this alert.....> []
 Send Alert to Pocket Office.....> []

[F2] Update [F8] List [F9] Prev [F10] Next

08/17/2004 08:35:58 Copyright Fujitsu-ICL Inc.

The cursor appears at the Number entry.

- 2 Type in the required alert number and press *Enter*.

Note

Developers of new functions take note of the ranges to use.

1 - 200	—	Reserved for POS terminal messages
201 - 1000	—	Reserved for Back Office messages
1001 - 2000	—	User programmable
5000 - 9999	—	Reserved to added as a key on the POS Menu

- 3 Enter the message description (two lines available) and press *Enter* to move to the next field. Fill in the required fields as explained below.

Field	Description
Timeout between Confirmation and Re-Alert	Set this parameter (minutes), to a high value, to avoid having the same alert pop up too frequently. For a critical type alert, set the value to 1 minute, the minimum.
Pop-Up Alert	Check this parameter to enable the red ALERT indicator at the bottom of the screen.
Pop-Up Message	Check this parameter to enable a pop-up message.
Password Required on Confirmation	If you want to prevent unauthorized personnel from accepting alerts, check this parameter. When a user attempts to confirm this alert, the Alert Confirmation window pops up and prompts for the user number and password. No access to menus is possible until the alert is confirmed.
Ignore this Alert	To ignore this alert, check the parameter. The alert is neither displayed nor logged.
Send Alert to Pocket Office	To enable the alert to be sent to a Pocket Office user, check the parameter.

- 4 Press *F2* to record the new alert.

Updating an Alert Type

This function allows you to update the details of an alert.

- 1 To update the details of an alert, highlight the required alert in the Alert Types Maintenance screen, and select *Update*.

The Alert - Update screen now displays with the details of the selected alert.

For field descriptions, see 'Adding a New Alert', above.

- 2 To enter new/updated data in a field, move the cursor to that field using the *Enter* or *Tab* key. Type or overwrite the new data.

If the field has item selection, press *F8* to select a new value.
For parameter fields, use the *Space Bar* to check or uncheck that field, as appropriate.

3 Press *F2* to record the changes.

➤ **To display another alert**

- Type in the alert number and press *Enter*; or
- Press *F8* to open the alert list window. Locate the required alert using the *PgUp*, *PgDn*, *Up Arrow* and *Down Arrow* keys. Press *Enter* to display its details.

➤ **To page through alerts**

- Press *F10* to display the next alert. Press *F9* to display the previous alert.

Deleting an Alert Type

This function is used to delete an alert from the alert file.

- 1 In the Alert Types Maintenance screen, highlight the alert to be deleted and select *deLete*. The Alert - Delete screen displays with the details of the selected alert.
- 2 Press *Enter*. In the delete confirmation box, select *Yes* to delete or *No* to retain the alert.

The functions available in the Alert - Delete screen are the same as those described in the Alert - Update screen. In other words, you can display and delete the previous (*F9*) or next alert (*F10*), or any other alert from the alert list (*F8*). If you know the number of the alert you want to delete, just type its number at the cursor position. After displaying the required alert, perform step 2 to delete.

Printing an Alerts Type List

Use this function to display and print a list of the alerts defined in the system.


- 1 In the Alert Types Maintenance screen, select *Print*. The Alert - Print screen displays the details of all the alerts, line by line.
- 2 To view all parts of the displayed list use the following:

- *Right Arrow* and *Left Arrow* to shift the screen in the arrow direction.
 - *Ctrl+Right Arrow* and *Ctrl+Left Arrow* to shift to the last column and first column.
 - *PgUp* and *PgDn* to page through the lines of the list.
- 3 Press *F10* to print the list.
 - 4 Press *F3* or *Esc* to return to the Alert Types Maintenance screen.

Alerts Parameters

Use this option to specify which PCs (MFS/workstation) are to receive and display alerts.

To access this option, select Alerts Parameters from the System Alerts menu. The Alerts Parameters screen displays.



This screen displays a list of all the possible PCs in the store, from MFS1 and 2 to LFS3 through 10. Use *Tab* to move to the required PC and press *Space Bar* to select it. To de-select, press *Space Bar* again.

Note:

You must have "Alerts in System" activated to use the Pocket Office RMA (Remote Manager Authorization) module.

Run POS Application (PIP)

This function, also known as PIP (POS in PC) is only available if it was set up during the installation of ISS45.

By using this option, you can operate the MFS1 or MFS2 (or any PC workstation) as a POS terminal. A cash drawer, printer, keyboard, customer display and other peripheral equipment as required, should be connected to the PC.

- To switch from PC (back office) mode to POS terminal mode (PIP), select Run POS Application from the Main menu.

The screen appears identical to that of a POS terminal.



You can now operate the PC as a normal POS terminal.

If a PIP was not defined during installation, an error message displays: Can not switch to POST from this PC.

- To exit from PIP mode back to PC mode, use the *Exit POS Function* key, or, on a regular keyboard, press *Ctrl+F10*.

Note

In a PIP configuration, switching back and forth between terminal and back office modes can prevent the POS terminal from running. This is due to the amount of memory available as well as a DOS limitation. To recover, you must exit to DOS and type in the command PCM.

Index

	%	
% Tare Weight Parameters (31-60) ..	92	
	2	
24 Hours Trading Store		
EOD Parameters.....	20	
2 nd PC number to use as CCMS		
Server		
Parameter.....	42	
2X20 Kbd Display		
POST configuration	136	
	A	
ACH Tender Numbe	123	
Action for Keyboard Functions.....	43	
Active		
Multiple Stamp Schemes	128	
Active keys		
LAN monitoring	198	
Add Amount		
Coupon parameter	152	
Additional template name to print		
on receipt bottom		
Receipt Printing Parameters ..	130	
Additional Tender Information.....	113	
Age Required		
POST parameter	87	
Alerts		
Log.....	236	
message	235	
Parameters.....	244	
Searching	238	
Types Maintenance	239	
Allow Cashier to select Specific Tax		
for Tax Exempt		
POST parameter	70	
Allow Cashier to select Specific Tax		
for Tax Reversal		
POST parameter	71	
Allow changing of trading date, next		
trading date, EOD type		
EOD Parameters.....	17	
Allow Coupons in Departments with		
No Sales in Order		
Coupon parameter	150	
Allow Declarations for		
Cashiers/Posts not Signed-on		
Parameter	28	
Allow delayed age verification		
POST parameter	86	
Allow Delayed POS Balancing		
Parameter	30	
Allow EFT reconciliation		
Post Configuration	143	
Allow E-O-Day Activation from a		
Workstation		
EOD Parameters.....	16	
Allow Foreign Currency Change		
POST parameter	53	
Allow Frequent Shopper discount		
higher than item price		
Parameter	34	
Allow manual weight		
POST parameters.....	62	
Allow Non Whole Dollar Food		
Stamps		
POST parameter	71	
Allow offline gift card activation		
Gift Cards	118	
Allow PLU Batch Activation by		
Date/Time		
Parameter	37	

Allow Promotion Batch Activation by Date/Time Parameter.....	39	Notes.....	19
Allow scanning of Member Card during a transaction Member Card parameters	109	Automatic insert in all tickets POST parameter	76
Allow transactions (pickups/loans) after cashiers/posts locked Parameter.....	28	Automatic insert in all tickets.....	76
Always read PLUs from PC POST parameter	56	Automatic Open Drawer at Sign on POST parameters.....	64
Any F/S Eligible Items Paid With F/S is Tax Forgiven POST parameter	71	Automatic Open Drawer at Sign-off POST parameters.....	65
Any F/S Tender Forgive Tax on All F/S Elig. Items (NJ) POST parameter	71	Automatic Secure Mode/Automatic Sign Off POST parameter	65
Apply Frequent Shopper discount also with any manual price entries POST parameter	76	Automatic tender of available balance for Gift Card	119
Apply Frequent Shopper discount also with any manual price entries	76	Automatically accept combine card as tender Member Card parameters	110
Apply Idle-Locking Mode for Pin Pad	99		
Assigning Privilege Passwords.....	188	B	
System Security Levels.....	188	Back Office parameters 2 nd PC number to use as CCMS Server	42
Audit File Record size Parameter.....	33	Allow Declarations for Cashiers/Posts not signed-on	28
AUTH file directory on the server	98	Allow Delayed POS Balancing	30
Auth. Port POST configuration	140	Allow Frequent Shopper discount higher than item price.....	34
Automatic EOD Parameters.....	21	Allow PLU Batch Activation by Date/Time.....	37
Automatic End of Day Checksum	176	Allow Promotion Batch Activation by Date/Time	39
exceptional dates	22	Allow transactions (pickups/loans) after cashiers/posts locked.....	28
next working date	22	Audit File Record Size	33
		Cashier/POST Locking allowed only to Printer & File or File...28	
		CCMS alias in HOSTS file.....	42
		CDV scheme for internal number	32

Date	9	Mix & Match Group, update if one PLU changed	32
Decimal Point Position	9	No. of tickets between retries of upgrade	47
Delay Cashier/Safe Over/Short Totals	28	Number of months to keep records in PACKAGES.QDX.	48
Delayed cashier balancing	27	PC number in system	11
Display current media in till on Cashier/POS Loan/Pickup....	28	PC Number to Activate Batch Files by Date/Time	39
Do Not Transfer Cashier Period on Sunday through Saturday	28	PC number to use as CCMS server	42
Do Not Transfer POS Period....	30	PC number to use as PCCS server	42
Echo Batch PLU Data on Screen	37	PLU and Promotion Batches	36
Eldat on System	42	PLU Batch File Name	37
End of Day	16	PLU Batch Type	38
Enhanced Bad Accounts, Store number CDV	10	PLU Follow Department Flags as a Default	32
Enhanced cashier/store balancing	27	PLU Maintenance Audit	33
Exclude Host batch changes from Audit Report	45	PLU Maintenance Audit File Name	33
Exclude Non-merchandise sales from department reports totals	44	PLU must have a valid Check Digit	31
Factura in System	10	PLU Report File Name	33
Host CCMS type	42	PLU Report File Record Size....	33
Internal Code in system	31	PLUs and Items	30
Item Includes Check Digit	33	Port number	42
Local CCMS type	42	POS Accountability in System ..	29
LPT number	13	Profit Report File Name	34
Max No. of seconds between retries of upgrade	47	Profit Report File Record Size ..	34
Max No. of seconds to wait for 2 nd PC Synchronization	47	Promotion Batch File Name	39
Max No. of seconds to wait for user confirmation	47	Rsession Active	48, 50
Max No. of tills to upgrade simultaneously from one server	49	Rsession communication time out	49
Mix & Match Group, maximum value	32	Save PLU Batches Before Execution	39
		Save Promotion Batches Before Execution	40
		Set Discount Prohibited Flag to [] if Item is on Promotion	35

Set Discount Prohibited Flag to [] if Item is on Reduction	35	Coupon parameter.....	160
Set Discount Prohibited Flag to [] if Item is on Sale.....	35	Barcode printing	
Set Discount Prohibited Flag to [] if Item is on Offer	36	Coupons	160
Show cashiers/POS by their sign-on date in Over Short report.	45	Barcoded tender active	
Show PLU Batch description in batch list	39	Barcode Tender	115
Store Number	9	Barcoded tender number	
Subdepartment in System	10	Barcode Tender	115
Transfer Cashier Period.....	28	Barcoded Tender Options.....	113
Transfer POS Period	30	Barcoded tender prefix	
Update ALL Items linked to internal code	31	Barcode Tender	115
Use ENTER key as the UPC key	36	Barcoded tender value length	
Use opcode #1 <new> as INSERT/UPDATE code	38	Barcode Tender	115
Use Original Batch Name for Error Batch File	38	Barcoded tender value location	
Warning Message, Disk space available	10	Barcode Tender	115
Weight.....	9	Batch files.....	39
Workstation in system	12	Battery Backup	
Zero price items change to manual price	36	POST configuration	137
Zero Price PLU Allowed.....	34	Biometric Options Parameters.....	121
Zero Sale Weeks.....	36	Birthday Validation Print Option	
Zero Sale Weeks Before Actual PLU Local Deletion	36	POST parameter.....	86
Back Office Parameters	7	Bonus coupons	152
VAT Number	9	Buffer Printing	
Bad Account File is resident on POST		Reorganize Receipt.....	104
POST parameters	61	Build an ASCII Transaction File during E-O-D	17
Bagger ID		EOD Parameters.....	17
POST configuration	143	Build audit seq file.....	214
Barcode Number		Build Credit ASCII File during E-O-D	
		EOD Parameters.....	16
		Build PLU File from Comm. File...	211
		BUY Qty field	155
		C	
		Calculate qualifying total	
		Trading Stamps.....	126
		Capture EBT GEN Number for manual account entry.....	98
		Card Value	
		Gift Cards	117

Cash in Drawer Limit		CC to allow coupon as first item in the ticket.....	151
POST parameters	59	CC to bypass 'cashier not found' during offline sign-on.....	82
Cash Office		CC to restrict redemption of Customer Accounts out of sale.....	81
Parameters.....	26	CC to restrict redemption of EAN 99 coupons out of sale.....	151
Cashier		CCMS alias in HOSTS file	
Post Configuration	141, 143	Parameter	42
Cashier age verification in use		CCMS LOG	
POST parameter	86	System Maintenance and Utilities	201
Cashier file is resident on POST		CCTV in System	196
POST parameters	60	CCTV Interface	196
Cashier Notification Icon Time Limit	43	CCTV Server Host Name	196
Cashier/POST Locking allowed only to Printer & File or File		CCTV Server Port.....	196
Parameter.....	28	CDV	
CC exceeding max gift cards purchased in a single order	118	Programming	169
CC for Customer Account insufficient funds	81	Schemes	169
CC for Customer Account not on file	81	CDV scheme for internal number	
CC for Customer Account off-line	81	Parameter	32
CC for exceeding max. amount in negative transactions	82	Ceiling Amount.....	153
CC for exceeding qty limit at scanning	82	Change Password Allowed at Sign Off	
CC for Maximum Amount in Drawer		POST parameter	65
Post Configuration	143	Change password allowed at sign-on	
CC for Minimum Amount in Drawer		POST parameters.....	64
Post Configuration	142	Charge Payment Tender	
CC for Minimum Purchase		POST parameter	56
Coupon parameters.....	159	Check digit verification	31
CC for overrideable decline		Check for second ID number in bad account	
EPS Payment Provider	98	POST parameters.....	62
CC for overrideable decline.....	98	Check Guarantee Functionality	
CC for Price Override on Gift Gard department range.....	118	POST parameters.....	58
CC for Save/Recall ticket in off-line mode	81	Check tender daily limits on account, amount	
		POST parameter	77

Check tender daily limits on account, amount.....	77	Keying Weighed Items	78
Check tender daily limits on account, count POST parameter	77	Control checks	
Check tender daily limits on account, count	77	Bypass Control Check if Conditions Met	78
Checkout bank Post Configuration	143	Bypassing WIC Check Amount	68
Checkout Bank Groups System Maintenance and Utilities	144	Bypassing WIC Expiration Date	68
Checksum	175	CC for Exceeding WIC Check Amount	68
Clear Screen LAN monitoring	198	Control Check for not Meeting Minimum Purchase for F/S....	74
Code in Use POST parameter	84	Control Check to Bypass Frequent Shopper.....	74
Code Management Parameters Parameters.....	46	Exceeding WIC Expiration Date	68
Combine Same Weighed Items.	105	Printer Paper Low	78
Compare and rebuild mix & match file	212	Control checks	
Compare and rebuild POST PLU file	213	Exceeding Cancel/Subtract Limit	78
Connected to printer	138	Control checks	
Control check for minimum purchase Minimum purchase amount required.....	156	Cancel/Subtract Limit Amount.....	78
Control check for minimum purchase.....	156	Control checks	
Control Check for not meeting minimum purchase for disc POST parameter	77	Transaction Void	79
Control Check for not meeting minimum purchase for disc	77	Control checks	
Control Check Options	78	Subtract Next During Item Registration.....	79
Control checks		Control checks	
Allow Coupons to Bring Subtotal < Zero.....	150	Item Cancel During Item Registration.....	79
		Control checks	
		Subtract Next/Item Cancel After Completion.....	79
		Control checks	
		Pressing Item Cancel During Template/Slip Print	79
		Control checks	
		Return Transactions, After Completion.....	79
		Control checks	
		No Sale Within a Transaction ...	79

Control checks		Cost Plus Programming.....	168
No Sale Outside a Transaction	79	Cost Plus Taxable Surcharge	
Control checks		Department	
Credit Card Tender that Exceeds		POST parameter.....	56
Eligible Amt.....	79	Coupon in Use	
Control checks		Coupon parameter.....	158
Saving Transactions with Partial		Coupon Mult.	
Tender.....	79	Coupon parameter.....	152
Control checks		Coupon parameters	
Price Override.....	79	Add Amount.....	152
Control checks		Allow Coupons in Departments	
Bypass Check Printing.....	79	with No Sales in Order.....	150
Control checks		Barcode Number.....	160
Bypass Check Endorsement....	80	CC for Minimum Purchase.....	159
Control checks		CC to allow coupon as first item	
Bypass Tender Template Printing		in the ticket.....	151
.....	80	CC to restrict redemption of EAN	
Control checks		99 coupons out of sale.....	151
Off-line Bad Account Request..	80	Ceiling Amount:.....	153
Control checks		Coupon in Use.....	158
Off-line Supervisor Request.....	80	Coupon Mult.	152
Control checks		Coupon Printing in use	156
Off-line ECCA Request.....	81	Coupon Value From-To	152
Control checks		Dept Net	149
Bypassing Birthday Prompt.....	86	Give Bonus Coupons on	
Control checks		Discountable Items Only.....	150
Restricted Sale	87	Graphic Logo	160
Control checks		Item/Department	159
Birthday Val.....	87	Item/Department Found/Not	
Control checks		Found in Basket	159
Allow More Coupons than Items		Item/Department Number.....	159
.....	150	Level of Coupon Validation	148
Convert 7.X Files to 7.3 Files.....	210	Markdown department for UPC5	
Cost Plus in system		coupons with 992 bypass code	
POST parameter.....	56		151
Cost Plus Non Taxable Surcharge		Maximum Coupon Face Value	
Department			150
POST parameter	56	Maximum number of coupons to	
Cost Plus Print Character		print per transaction.....	156
Sign	93	Minimum Order	152

Minimum purchase amount required.....	159	Sign	93, 95
Minimum purchase amount required.....	156	Current and next working dates resetting.....	200
No keyboard sound for coupons without department or price	151	<i>current period</i>	27
Print Barcode	160	Customer Display	
Show the above CC if ticket amount is less than the minimum purchase amount by	160	Post Configuration	140
Sun - Sat:	153	Customer Display Messages	101
Tax Forgive	148	Customer Slip Template Name ..	131
Tender Number	152	Customized EFT Message on Cashier Display	123
Tender Number for EAN 99 coupons	151		
Tender Number for UPC5 coupons	151	D	
Tender Number for Vendor, Store and Bonus Coupons	151	Date and Time	
Ticket amount to print coupon....	159	Automatic End of Day	199
Validate EAN99 as UPC5.....	151	Date and Time setup.....	199
Coupon Parameters	148	Date, American/European Parameter	9
Coupon Printing in use.....	156	Days to keep Electronic Journal transaction history EOD Parameters.....	17
Coupon Printing Parameters System Maintenance and Utilities	156	Debug	
Coupon Value From-To Coupon parameter	152	LAN monitoring	198
Coupons		Debug Mode	
Bonus coupon	146	POST configuration	142
Coupon parameters	146	Decimal	
Coupon printing	157	Sign	93
Coupon values.....	154	Decimal Places	
Store Coupon	146	POST parameter	84
UPC5.....	154	Decimal Point Position	
Vendor Coupon.....	146	Parameter	9
Credit File ASCII Name		Default Minimum Purchase Amount for Promotions	
EOD Parameters.....	16	POST parameter	54
Currency		Define	
		QuickDex Files.....	203
		Delay (in seconds) for Open Drawer Alarm after Sign-Off	
		POST parameters.....	65
		Delay Cashier/Safe Over/Short Totals	

Parameter.....	28	Display Member card name on	
Delay POS/Safe Over/Short Totals		customer display	
.....	30	Member Card parameters	110
Delayed cashier balancing		Display Member Name from	
Parameter.....	27	Corima	
Department Number		Member Card parameters	111
POST parameter	86	Display Member name on cashier	
Department Repeat Key in Use		display	
POST parameter	53	Member Card parameters	109
Dept Net		Display Member name on customer	
Coupon parameter	149	display	
Design POS Menus.....	164	Member Card parameters	109
Digits in Price		Display queue length every 'n'	
POST parameter	84	minutes	
Disallow Quantity with Scanning		Post Configuration	143
POST parameters	57	Display/Print points with decimal	
Discount Account Options.....	77	point	
Discounts.....	35	Trading Stamps.....	126
Display Captured Signature on		Do not allow sales in tender mode	
Cashier Display with Accept or		POST parameter	54
Reject.....	63	Do Not Print Expiration Date on	
Display current media in till on		Receipt	63
Cashier/POS Loan/Pickup		Do not prompt for Frequent	
Parameter.....	28	Shopper at the beginning of a	
Display EFT Payment Icon on		ticket.....	75
Cashier Display	123	POST parameter	75
Display Eligible Benefits Only	69	Do Not Transfer Cashier Period on	
Display F/S total after F/S tender		Sunday through Saturday	
POST parameter	56	Parameter	28
Display Loyalty Member Name from		Do Not Transfer POS Period	
Biometric Identification	122	Parameter	30
Display Member card description		Don't Print POS Reports during	
on cashier display		End-of-Day	
Member Card parameters	110	POST parameter	56
Display Member card description		Don't print tax report if tax is zero	
on customer display		POST parameter	71
Member Card parameters	110	Don't display message on operator	
Display Member card name on		screen	
cashier display		Trading Stamps.....	126
Member Card parameters	110	Don't print price in PLU group list	

POST parameters	57
Drawer	
POST configuration	138
Dual Drawer in use	138

E

EAN 99 coupon in system	
POST parameter	54
EBT WIC in System	69
EBT WIC Tender Numbe	69
ECC Template Name	121
ECC Tender Number	120
Echo Batch PLU Data on Screen	
Parameter	37
EFT Location	
POST configuration	143
Electronic Check Conversion	119
Electronic Journal	229
Electronic Payment Settings	98
Enable Check Flip	
Post Configuration	139
Enable Healthcare Item	
Substantiation	124
End of Day	18
Parameters	16
End of Day types	
End of month	18
End of week	18
End of year	18
End time	
Multiple Stamp Schemes	128
Enhanced Bad Accounts, Store	
number CDV	
Parameter	10
Enhanced cashier/store balancing	
Parameter	27
Enhanced Frequent Shopper	
System Maintenance and Utilities	
.....	73
Enhanced Promotion description	
Member Promotion	112
EPS Payment Provider	98
EPS Payments	
EPS Payment Provider	98
Euro Rate	
POST parameters	61
exceptional dates	
Automatic EOD	22
Exclude Host batch changes from	
Audit Report	
Parameter	45
Exclude Non-merchandise sales	
from department reports totals	
Parameter	44

F

Factura in System	
Parameter	10
Field Engineer's Utilities	201
File extensions	
QDX	191
Zip	191
File Selection screen	191
File Type	
FIFO	205
Index	205
Relative	205
Relative expansion	205
Super index	205
Food Stamp Print Character	
Sign	93
Food Stamp Tender Number	
POST parameter	71
Foodstamps in drawer limit	
POST parameters	59
Force Department/Price Entry of	
Unknown Items	
POST parameter	54
Force Supervisor ID barcode when	
supervisor intervention is required	63

Force ZEROS on Coupon Number POST parameters	58
Forgive Tax on F/S Partial Tenders by Highest Tax Rate	71
Forgive Tax on Vendor Coupons if F/S Tendered.....	71
Format Sign	93
Freeze LAN monitoring	197
Freq. Shop. Feature in Use POST parameter	72
Freq. Shop. Merchandising Feature POST parameter	74
Freq. Shop. Minimum Purchase Amount POST parameter	74
Freq. Shop. Range POST parameter	73
Frequent Shopper Discount	94
Frequent Shopper discount to be applied to per item price (MSU) POST parameter	75
Frequent Shopper discounts do not reduce net sales POST parameter	76
Frequent Shopper discounts do not reduce net sales.....	76
Frequent Shopper dummy card number POST parameter	76
Frequent Shopper dummy card number.....	76
Frequent Shopper Print Character Sign	94
Frequent Shopper receipt template same as member promotion POST parameter	76

Frequent Shopper receipt template same as member promotion	76
Function Maintenance	215
Usage Report	227

G

General function	220
General POST Parameters 1 2 3 4	51 55 58 61
Generate sound from Post Configuration	137
Get Value field.....	155
Gift Card Activation After Tender	118
Gift card activation tender number	118
Gift Card in System Gift Cards	117
Gift Card Options	117
Give Bonus Coupons on Discountable Items Only Coupon parameter.....	150
Graphic Logo Coupon parameter.....	160
Graphic Logo POST configuration	142
Graphic Logo Maintenance	230

H

Header/Footer Defining.....	180
Linking to POS	183
Maintenance	179
POST configuration.....	142

Hooks.....	100
Host CCMS type Parameter.....	42

I

Ignore this Alert Alert Maintenance	242
In-house account type POST parameters	59
Internal Code in system Parameter.....	31
Item Includes Check Digit Parameter.....	33
Item/Department Coupon parameter	159
Item/Department Found/Not Found in Basket Coupon parameter	159
Item/Department Number Coupon parameter	159

K

Keyboard privilege	224
Programming	215
Sale mode	220
Tender mode	220
Keyboard layout Updating	225
Keyboard Layout Copying	226
Defining	219
Deleting.....	226
Keyboard Report Printing	227
Key-in Fly Buys number without check digit POST parameters	61

Key-in Member Card number without check digit Member Card parameters	109
Keylock positions	224

L

LAN Comm LAN monitoring	199
LAN monitoring	197
Layout No. POST parameter	87
Length of secondary ID number Member Card parameters	110
Level of Coupon Validation Coupon parameter	148
Level of Detail on Audit Printer POST parameter	53
Limit F/S eligible to Bal. Due POST parameters	71
Link POS to Keyboard	227
Local CCMS type Parameter	42
Log parameter User access	190
LPT number Parameter	13

M

Manual Check Tender Number ..	120
Markdown department for UPC5 coupons with 992 bypass code	151
Mask User ID and Password when supervisor intervention is required	63
Max amount for gift cards purchased in a single order.....	118
Max No. of seconds between retries of upgrade	

Parameter.....	47	Menus, POS	
Max No. of seconds to wait for 2 nd		designing	164
PC Synchronization		MFS1	11
Parameter.....	47	MFS2	11
Max No. of seconds to wait for user		MICR reader in use	
confirmation		Post Configuration	138
Parameter.....	47	Minimum Amount in Drawer	
Max No. of tills to upgrade		Post Configuration	142
simultaneously from one server		Minimum Amount of Transaction to be	
Parameter.....	49	Included in Customer Count.....	131
Max number of gift cards		Minimum Order	
purchased in a single order	118	Coupon parameter.....	152
Maximum amount for negative		Minimum purchase	
transactions.....	82	Multiple Stamp Schemes.....	128
Maximum Amount in Drawer		Minimum purchase amount for	
Post Configuration	142	transaction discounts	
Maximum Coupon Face Value		POST parameter	77
Coupon parameter	150	Minimum purchase amount for	
Maximum items in express orders		transaction discounts	77
POST parameters	62	Minimum purchase amount	
Maximum number of coupons to		required	156
print per transaction.....	156	Minimum Purchase Amount	
Member Card		Required	
Parameters.....	108	Coupon parameters.....	159
Member Card in system		Minus	
Member Card parameters	109	Sign	93
Member Card name in system		Minutes to Wait for POS to Send	
Member Card parameters	109	Remaining Transactions	
Member Card number includes		EOD Parameters.....	20
check digit		Mix & Match	
Member Card parameters	109	Code	32
Member Card qualifies for Frequent		Mix & Match Group, maximum	
Shopper prices		value	
POST parameter	76	Parameter	32
Member Card qualifies for Frequent		Mix & Match Group, update if one	
Shopper prices	76	PLU changed	
Member Promotion.....	111	Parameter	32
Member Promotion discounts do		MobileLime	132, 133
not reduce net sales		MobileLime Discount Number ...	133,
Member Promotion	112	135	

MobileLime Prefix of Terminal ID	133, 134
MobileLime Timeout	133, 134
Monitor Type	
POST configuration	137
MSU Rounding Option	
POST parameter	53
Multiple Language in System	
POST parameter	55
Multiple Stamp Schemes	126
Multiple Tax Print Character	
Sign	93
Multiplication calculation method	
Trading Stamps	125
Multiplication factor	
Multiple Stamp Schemes	128

N

next working date	
Automatic EOD	22
No CDV Check on Item	
Scan/ENTER Key	
POST parameter	54
No keyboard sound for coupons	
without department or price	151
No UPC5 in System	
POST parameter	54
No. of tickets between retries of upgrade	
Parameter	47
Non Cost Plus Print Character	
Sign	94
Non Food Stamp Print Character	
Sign	93
Non Frequent Shopper Print Character	
Sign	94
Non Taxable Print Character	
Sign	93
Non-Rx Print character	124

Number of digits for Charge Posting account numbers	
POST parameter	77
Number of digits for Charge Posting account numbers	77
Number of Digits for Department Value	
POST parameters	59
Number of Digits for Media Value	
POST parameters	59
Number of Minutes Before Automatic Secure Mode	
POST parameter	65
Number of months to keep records in PACKAGES.QDX	
Parameter	48
Number of Rates to Accumulate Amounts	
POST parameter	70

O

Open Drawer in Training Mode	
POST parameter	52
Open Drawer on End Of Day	
POST parameters	52
Open Drawer on Tender Purchase	
POST parameter	52
Open Drawer Timeout	
POST parameters	52

P

Package Status Maintenance	49
Parameters	
Back Office	7
Cash Office	26
Code Management Parameters	46
Discount, Account Options	77
End of Day	16
EOD Job Stream Reports	23

General Back Office	9		
General POST Parameters 1	51		
General POST Parameters 2	55		
General POST Parameters 3	58		
General POST Parameters 4	61		
PCs in System	11		
PLU and Promotion Batches	36		
PLUs and Items	30		
POST Parameters 1	51		
POST Parameters 2	96		
Printers in System	12, 13, 14		
Rounding	107		
Rsession Parameters	48		
Sign On/Off, Secure	64		
System	6		
System Integrity	172		
Tax, Food Stamp Options	70, 72		
WIC Options	67		
Password			
Privilege levels	189		
Password Required at Sign On			
POST parameter	64		
Password required at sign-off			
POST parameters	65		
Password Required on			
Confirmation			
Alert Maintenance	242		
Password required with cashier			
bar-code			
POST parameters	59		
Passwords			
Definition	184		
'Payment amount' prompt defaults			
to 'balance due' amount			
POST parameters	61		
		P	
		PC Number in system	
		Parameter	11
		PC Number to Activate Automatic	
		E-O-D	
		EOD Parameters	20
		PC Number to Activate Batch Files	
		by Date/Time	
		Parameter	39
		PC number to use as CCMS server	
		Parameter	42
		PC number to use as PCCS server	
		Parameter	42
		PCDV Req'd.	
		POST parameter	84
		PCs in System	
		Parameters	11
		Pending Redemption Start Date	
		Member Card parameters	108
		Perform Checksum during End-of-	
		Day	
		POST parameter	56
		Phone Cards	117
		PinPad Customer Display	63
		PIP (POS in a PC)	245
		PLU and Promotion Batches	
		Parameters	36
		PLU Batch File Name	
		Parameter	37
		PLU Batch Type	
		Parameter	38
		PLU Follow Department Flags as a	
		Default	
		Parameter	32
		PLU Maintenance Audit	
		Parameter	33
		PLU Maintenance Audit File name	
		Parameter	33
		PLU must have a valid Check Digit	
		Parameter	31

PLU Number for recharging		Copying	144
Gift Cards	118	Debug mode	142
PLU Range		Drawer	138
Gift Cards	117	Header/Footer	142
PLU Report File Name		Monitor Type.....	137
Parameter.....	33	Printer Type	138
PLU Report File record size		Scale Baud Rate	140
Parameter.....	33	Scale IRQ.....	140
PLU/UPC/Enter repeat key in use		Scale Port.....	139
POST parameter	53	Scale type	142
PLUs and Items		Scale Type	139
Parameters.....	30	Scanner Baud.....	139
Poll List Program.....	177	Scanner Bits	139
Pop-Up Alert		Scanner Handshake.....	139
Alert Maintenance	242	Scanner Parity.....	139
Pop-Up Message		Touch Screen Type	137
Alert Maintenance	242	Weight on TeamPOS	137
Port		POST parameter	
Post Configuration	138	Default Minimum Purchase	
Port for print commands		Amount for Promotions	54
Post Configuration	138	POST parameters	
Port number		Age Required.....	87
Parameter.....	42	Allow Cashier to select Specific	
POS		Tax for Tax Exempt	70
Closed Menu.....	165	Allow Cashier to select Specific	
Menus, designing.....	164	Tax for Tax Reversal	71
Post Configuration	141, 143	Allow delayed age verification ..	86
Sales Menu	168	Allow Foreign Currency Change	
Supervisor Menu.....	168		53
POS Accountability in System		Allow Non Whole Dollar Food	
Parameter.....	29	Stamps	71
POS keyboard		Always read PLUs from PC.....	56
Programming	215	Any F/S Eligible Items Paid With	
POS O/S Type		F/S is Tax Forgiven	71
Post Configuration	143	Any F/S Tender Forgive Tax on	
POST configuration.....	135	All F/S Elig. Items (NJ	71
2X20 Kbd Display	136	Automatic Secure	
Auth. Port	140	Mode/Automatic Sign Off.....	65
Bagger ID	143	Birthday Validation Print Option	86
Battery Backup	137	Cash in Drawer Limit.....	59

Cashier age verification in use.....	86
Change Password Allowed at Sign Off.....	65
Charge Payment Tender	56
Code in Use	84
Cost Plus in System	56
Cost Plus Non Taxable Surcharge Department.....	56
Cost Plus Taxable Surcharge Department	56
Decimal Places.....	84
Department Number	86
Department Repeat Key in Use.....	53
Digits in Price.....	84
Display F/S total after F/S tender	56
Do not allow sales in tender mode	54
Don't Print POS Reports during End-of-Day Reports.....	56
EAN 99 coupon in system	54
Food Stamp Tender Number ...	71
Force Department/Price Entry of Unknown Items.....	54
Freq. Shop. Feature in Use	72
Freq. Shop. Merchandising Feature	74
Freq. Shop. Minimum Purchase Amount	74
Freq. Shop. Range	73
Layout No.	87
Level of Detail on Audit Printer	53
MSU Rounding Option	53
Multiple Language in System...	55
No CDV Check on Item Scan/ENTER Key	54
No UPC5 in System.....	54
Number of Minutes Before Automatic Secure Mode.....	65
Number of Rates to Accumulate Amounts	70
Open Drawer in Training Mode	52
Open Drawer on Tender Purchase	52
Password Required at Sign On	64
PCDV Req'd.	84
Perform Checksum during End-of-Day	56
PLU/UPC/Enter repeat key in use	53
Price or Weight.....	84
Print F/S Subtotal on Receipt if F/S tendered.....	71
Prompt to Accept Birthday.....	86
Report Required at Sign Off.....	65
Reset POS counter during End-of-Day	55
Restricted Sale/Birthday Feature in Use:.....	86
Reversal Charge Payment Tender	56
Second Tender for Payouts/Receipts	54
Subtract Cashier Declarations from POS Reports	56
Tax Rates to be set ON for the Tax Reversal	70
Total or Individual Tax on Receipt	70
Type of Extended Balance Due to Display	55
Use Freq. Shop. No. for Check Tender Account Number	73
Void Transaction at.....	54
WIC Print Options	68
WIC Prompt Options	68
POST Parameters	
1	51
2	96

POST parameters Don't print tax report if tax is zero	71	Print 'PLU not found' slip Receipt Printing Parameters...	130
POST User Hooks	100	Print saving total on receipt when buffer printing is turned off Receipt Printing Parameters...	131
Preset function	222	Print separate receipts for each tender on pick-ups Receipt Printing Parameters...	130
<i>previous period</i>	27	Print Tare Weight on Receipt.....	131
Price or Weight POST parameter	84	Print Text to Transaction File POST configuration	143
Print 'Bal. Due' after each tender Receipt Printing Parameters ..	129	Print Total Number of Items on Receipt Receipt Printing Parameters...	130
Print 'Bal. Due' each time subtotal is pressed Receipt Printing Parameters ..	129	Print unique invoice number on charge posting tickets POST parameters.....	57
Print Barcode Coupon parameter	160	Printer Post Configuration	138
Print cashier name on receipt Receipt Printing Parameters ..	130	Printer Type POST configuration	138
Print coupons report on ticket Receipt Printing Parameters ..	129	Printers in System Parameters	12, 13, 14
Print currency on check Sign	94	Priority.....	186, 189
Print currency symbol on receipt Receipt Printing Parameters ..	129	Privilege.....	189
Print Customer Slip After	131	Level.....	188
Print duplicate receipt on loans and pickups Receipt Printing Parameters ..	130	Password	188
Print F/S Subtotal on Receipt if F/S tendered POST parameter	71	Setup.....	188
Print Frequent Shopper discount total only (no details) POST parameter	76	Process Cashier Transaction handling parameter	163
POST parameter	76	Process Memory Transaction handling parameter	163
Print Member name on receipt Member Card parameters	110	Process PLU transactions Transaction handling parameter	162
Print Offer Progress on Receipt Even if Promotion Was Not Triggered	111	Profit Report File Name Parameter	34
Print 'PLU not found on inquiry' slip Receipt Printing Parameters ..	130	Profit Report File record size	

Parameter.....	34
Profitability report.....	34
Program Keys	218
Promotion Batch File Name	
Parameter.....	39
Prompt for customer's ID on Save Transaction	
POST parameters	60
Prompt for Frequent Shopper on U-Scan	63
Prompt for Member Secondary ID at the Pin Pad	63
Prompt to Accept Birthday POST parameter	86
Purchase amount required for one stamp	
Trading Stamps.....	125

Q

Q-Buster.....	132
Q-Buster in system	
Q-Buster	132, 133, 134
QDEX	
File name.....	205
Maximum Records.....	206
Record Size	205
QDX	
File extension.....	191
QDX Files Checksum Table.....	175
Qualified Spend Option	
Member Card parameters	109
Queue length threshold alert (count)	
Post Configuration	143
Queued alerts	235
QuickDex	
Definition.....	202
File Parameters	205
File server.....	202
Memory files.....	202

QuickDex General Parameters	
Define	209

R

Receipt Header/Footer Maintenance	179
Receipt Line Spacing	
Receipt Printing Parameters...	131
Record/Playback Keys	193
Redemption End Date	
Member Card parameters	108
Redemption Option	
Member Card parameters	109
Redemption points value	
Member Card parameters	109
Redemption Tender	
Member Card parameters	108
Reorganize Receipt.....	103
Reorganize Receipt options	
Buffer Printing.....	104
Combine same items	104
Main sort.....	105
Omit voided and canceled items	105
Second sort.....	105
Sort receipt.....	105
Your savings today	105
Report Required at Sign Off	
POST parameter	65
Reset POS counter during End-of-Day	
POST parameter	55
Restricted Sale	
Layouts	87
Times	89
Restricted Sale Special Dates	90
Restricted Sale/Birthday Feature in Use	
POST parameter	86
Restricted Sale/Birthday Validation ..	85

Retailer information.....	99
Retrieve DOB from Biometric Identification for Age Verification	122
Retrieve Loyalty Information from Biometric Identification	122
Reversal Charge Payment Tender POST parameter	56
RMA Cashier Notification.....	43
Rounding	107
Rounding Parameters.....	107
Rsession Active Parameter.....	48
Rsession communication time out Parameter.....	49
Rsession Parameters Parameters.....	48
Run POS Application	245
Rx Print character	124

S

Sales Printer Sound POST parameters	59
Save PLU Batches Before Execution Parameter.....	39
Save Promotion Batches Before Execution Parameter.....	40
Scale Baud Rate	140
IRQ	140
Port.....	139
Post Configuration	139
Type	139
Scale Type POST configuration	142
Scanner Post Configuration	139
Scanner Baud	

POST configuration	139
Scanner Bits POST configuration	139
Scanner Handshake POST configuration	139
Scanner Parity POST configuration	139
Scanning qty limit.....	82
Screen Saver Setup System Maintenance and Utilities	232
Second Tender for Payouts/Receipts POST parameter.....	54
Seconds before Credit Card Number can be Entered POST parameters.....	58
Secure mode	65
Security authorization levels.....	187
level.....	183
Security Maintenance	183
Self Checkout Post Configuration	143
Send Pay Path totals during E-O-D EOD Parameters.....	17
Service Fee Programming	170
Set Discount Prohibited Flag to [] if Item is on Offer Parameter	36
Set Discount Prohibited Flag to [] if Item is on Promotion Parameter	35
Set Discount Prohibited Flag to [] if Item is on Reduction Parameter	35
Set Discount Prohibited Flag to [] if Item is on Sale Parameter	35
Set Priority	189

Show cashiers/POS by their sign-on date in Over Short report Parameter.....	45	Store Number Parameter	9
Show Only Alerts From the Last ...Hours.....	43	Subdepartment in System Parameter	10
Show PLU Batch description in batch list Parameter.....	39	Subtract Cashier Declarations from POS Reports POST parameter.....	56
Show the above CC if ticket amount is less than the minimum purchase amount by Coupon parameter.....	160	Sun - Sat Coupon parameter.....	153
Sign On/Off, Secure Parameters.....	64	Supervisor Privileges POST parameters.....	59
Signature Capture Tenders	116	Suppress Fly Buys check digit on receipt & transaction POST parameters.....	59
Signs	92	Suppress printing points on receipt Receipt Printing Parameters...130	
Cost Plus	93	System Security levels	187
Currency.....	93, 95	Security Levels.....	188
Decimal.....	93	System Alerts	235
Food Stamp Print Character	93	System Integrity	172
Format.....	93	foreground/background loading	174
Frequent Shopper Print Character.....	94	parameters.....	173
Minus.....	93	System Integrity in System.....	174
Multiple Tax Print Character.....	93	System Maintenance and Utilities.....	6
Non Cost Plus Print Character.	94	CCMS LOG.....	201
Non Food Stamp Print Character	93	Checkout Bank Groups	144
Non Frequent Shopper Print character.....	94	Coupon Printing Parameters.....	156
Non Taxable Print Character....	93	Enhanced Frequent Shopper....	73
Print currency on check	94	Screen Saver Setup	232
Software Key Information System Maintenance and Utilities	177	Software Key Information.....	177
Sort Promotion Add/Loss report by ID		System Parameters.....	6
EOD Job Stream	25	Setting.....	7
Start time Multiple Stamp Schemes	128		
		T	
		Tare Weight Parameters (1-30)	90
		Tax	70
		Tax Forgive Coupon parameter.....	148

Tax Rates to be set ON for the Tax Reversal POST parameter 70	Total or Individual Tax on Receipt POST parameter 70
Tax report to follow POS report POST parameters 56	Touch Screen Type POST configuration 137
Tax, Food Stamp Options 70, 72	Trading Stamp Parameters 124
Template name (text) to print of receipt Trading Stamps 126	Trading Stamps in system Trading Stamps 125
Template Name for FSA Disclaimer 124	Transaction File 191
Template Name for FSA totals .. 124	Transaction handling parameters Process Cashier 163
Tender for Rounding POST parameters 57	Process Memory 163
Tender Number Coupon parameter 152	Process PLU transactions 162
Tender Number for EAN 99 coupons Coupon parameter 151	Transaction version 162
Tender Number for UPC5 coupons Coupon parameter 151	Transaction Handling Parameters 161
Tender Number for Vendor, Store and Bonus Coupons Coupon parameter 151	Transaction version Transaction handling parameter 162
Thermal Printer 160	Transfer Balances For Inactive POS 30
Ticket Amount to Print Coupon Coupon parameters 159	Transfer Cashier Period Parameter 28
Time: Sunday through Saturday.. 21	Transfer POS Period Parameter 30
Timeout between Confirmation and Re-Alert Alert Maintenance 242	Transfer totals System default 28, 30
Times to Swipe Card before Manual Entry POST parameters 58	Type POST configuration 141, 143
Total Enhanced Promotion description Member Promotion 112	Type of Extended Balance Due to Display POST parameter 55
Total for Member Promotion description Member Promotion 112	
	U
	UPC5 Coupons 154
	UPC5 coupons Tender numbers 151
	Update ALL Items linked to internal code Parameter 31

Use Biometric Identification	
Functionality.....	122
Use ENTER key as the UPC key	
Parameter.....	36
Use ENTER Key as Total	
POST parameters	53
Use Freq. Shop. Dummy card	
POST parameter	76
Use Freq. Shop. Dummy card	76
Use Freq. Shop. No. for Check	
Tender Account Number	
POST parameter	73
Use Frequent Shopper number as	
member card number	
POST parameter	75
Use Frequent Shopper number as	
member card number	75
Use member card as Q-Buster card	
Q-Buster	133, 134
Use Member Card as Q-Buster	
Card.....	132
Use MTX Receipt Data	106
Use opcode #1 <new> as	
INSERT/UPDATE code	
Parameter.....	38
Use opcode #2 <update> as	
INSERT/UPDATE code	
Parameter.....	38
Use opcode #2 <update> as	
INSERT/UPDATE code	38
Use Original Batch Name for Error	
Batch File	
Parameter.....	38
User	
Adding	185
User Access Log	190
User IDs, passwords	
Security Maintenance	183
Users Inquiry	187
Users Password Definition	184

V

Valid Days.....	50
Validate EAN99 as UPC5.....	151
Var. Price/Weight Item Codes	
1	83
2	84
VAT Number.....	9
Verify weight changes at last	
keystroke	62
Void Transaction at.....	54


W

Warning Message, Disk space	
available	
Parameter	10
Watch File	
LAN monitoring	198
Weight	
Parameter	9
Weighed item.....	90
Weight on TeamPOS	137
WIC Date	
POST Parameters	68
WIC Options.....	67
WIC Print Options	
POST parameter	68
WIC Prompt Options	
POST parameters.....	68
WIC Validity Period	
POST parameters.....	69
Workstation in system	
Parameter	12

Z

Zero price items change to manual	
price	
Parameter	36
Zero Price PLU Allowed	
Parameter	34

Zero Sale Weeks		Parameter	36
Parameter.....	36	ZIP	
Zero Sale Weeks Before Actual		File extension	191
PLU Local Deletion			



© StoreNext Retail Technologies LLC 2010

StoreNext Retail Technologies LLC endeavors to ensure that the information in this document is correct and fairly stated but does not accept liability for any error or omission.

The development of StoreNext products and services is continuous and published information may not be up to date. It is important to check the current position with StoreNext. This document is not part of a contract or license save insofar as may be expressly agreed.