

Technical Bulletin

ISS45 Setup for Supervisor Scan Cards

ISS45-TECH-06:13

June 6, 2006

Supervisor bar-codes work off the privileges that are set in the Control Checks and the Cashier record.

The bar-code of the type 8888SSSSCCCC(K) is used for this function only.

- The SSSS is the 4 digit store number.
- If the store number is 4, the number will have 88880004CCCC(K).
- The CCCC is the 4 digit cashier number.

This will be the cashier number of the manager or person that will have this card. If the number is 112, the bar-code will now look like 888800040112(K)

NOTES

- You must have a check digit (K) on the end of the printed bar-code. If you do not have a utility or program to calculate the check digit, you can use the Coupon Printing Maintenance in ISS45. In the Bar-code field type in 888800040112 and press ALT-K for check digit. The system will input the correct check digit.
- The example bar-code listed above can only be used at store #4. If this card was scanned at another store, you will see a message 'Incorrect Store Number.'
- If you need a bar-coded card that will work at all stores, use the 9999 in place of the store number.
- You must set the Control Check as a Warning Only with a privilege of 1 to 8.
- You must also have the cashier number that is on the bar-code set to have the same privilege as the control check.
- At the POS, the control check will display, you press the Clear key and it will ask for Supervisor Number and Password, at this point scan the card. You can also type in your number and password manually.

This document and information are supplied to StoreNext Retail Technologies personnel and third parties to assist them in doing business with StoreNext. They are not to be used or distributed for any other purpose.

StoreNext Retail Technologies LLC endeavors to ensure that the information in this document is correct and fairly stated, but does not accept liability for any error or omission.