

Technical Bulletin

ISS45 Fuel Installation Registry Entries

ISS45-TECH-10:13

May 13, 2010

There are several ISS45 registry entries that must be applied to the system when installing the ISS45 V8 Fuel option.

A new zip file, available from the StoreNext Dealer Support Web site, contains the required standard registry files. [Click here to get the file.](#)

Unzip the files into a directory somewhere on the PFS, open Windows Explorer and then double click each file individually.

The following entries will be added to the PFS registry:

EXTTRS32

[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\ExtTrs32\Cmos]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\ExtTrs32\DataBase]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\ExtTrs32\EndOfDay]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\ExtTrs32\GeneralParam]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\ExtTrs32\Log]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\ExtTrs32\Paths]

FUELCOMPONG

[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\FuelCompMng]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\FuelCompMng\GeneralParam]

MTXLINKSERVER

[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\MTXLinkServer]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\MTXLinkServer\GeneralParameters]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\MTXLinkServer\MTXNetWork]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\MTXLinkServer\WorkingParameters]

[continued on next page...]

This document and information are supplied to StoreNext Retail Technologies personnel and third parties to assist them in doing business with StoreNext. They are not to be used or distributed for any other purpose.

StoreNext Retail Technologies LLC endeavors to ensure that the information in this document is correct and fairly stated, but does not accept liability for any error or omission.

ROUTESRV

[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\ActiveLinkServerList]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\ActiveLinkServerList\ActiveLinkServer01]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\ActiveLinkServerList\ActiveLinkServer02]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\ActiveLinkServerList\ActiveLinkServer03]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\ActiveLinkServerList\ActiveLinkServer04]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\ActiveLinkServerRangeList]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\ActiveLinkServerRangeList\ActiveLinkServer01]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\Database]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\GeneralParameters]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\RequestTypes]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\RequestTypes\RequestType01]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\RequestTypes\RequestType02]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\RequestTypes\RequestType03]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\RequestTypes\RequestType04]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\RequestTypes\RequestType05]
[HKEY_LOCAL_MACHINE\SOFTWARE\Pointofsale\RouteSrv\RequestTypes\RequestType06]

