



## Solidcore Demo Installation

1. Sign onto the system as Administrator
2. Close all open windows
3. Insert ISS45 parallel or USB key with Solidcore option on it. SETUP.EXE will not run with out the key being there.
4. Place the CD in the CD-ROM drive and double click on SETUP.EXE
5. Click on NEXT
6. Read the license agreement, click on I ACCEPT THE... and then click on NEXT
7. Enter the user name, organization name and serial number (use 0710-2208-1402-0108-2708 for StoreNEXT Solidcore), then click on NEXT
8. Click on NEXT to accept the default install folder
9. Click on INSTALL and when the installation completes click on FINISH
10. Double click on the **StorennextIntegrate.bat** file, when this function completes, close any open applications and remove the CD from the CD-ROM drive
11. Double click on the Solidcore 3 Command Line icon the desktop or click START| PROGRAMS| SOLIDCORE 3| SOLIDCORE 3 COMMAND LINE
12. Key in the following and then depress ENTER:  
sadmin solidify
13. When the solidify function has completed key in the following and depress ENTER:  
sadmin status
14. The following should appear:  
Solidcore protection: Disabled  
Solidcore protection on reboot: Disabled  
  
System Controller: Disconnected  
Local CLI access: Recovered  
[volume] [fstype] [status] [driver status]  
C:\ NTFS Solidified Unattached  
Etc.

15. Key in the following and then depress ENTER:  
sadmin enable

16. When the solidify function has completed key in the following and depress  
ENTER:  
sadmin status

17. The following should appear:

Solidcore protection:	Disabled		
Solidcore protection on reboot:	Enabled		
System Controller:	Disconnected		
Local CLI access:	Recovered		
[volume]	[fstype]	[status]	[driver status]
C:\	NTFS	Solidified	Unattached
Etc.			

18. Reboot the computer

19. Double click on the Solidcore 3 Command Line icon the desktop or click START|  
PROGRAMS| SOLIDCORE 3| SOLIDCORE 3 COMMAND LINE

20. When the solidify function has completed key in the following and depress  
ENTER:  
sadmin status

21. The following should appear:

Solidcore protection:	Enabled		
Solidcore protection on reboot:	Enabled		
System Controller:	Disconnected		
Local CLI access:	Recovered		
[volume]	[fstype]	[status]	[driver status]
C:\	NTFS	Solidified	Attached
Etc.			

22. The installation is complete