



ISS45 Trickle Feed User Reference

ISS45 8.1.7.0



ISS45 Trickle Feed User Reference

Date of Issue	Product Identification Number	Part Number	Brief Description
June 2005	45001/094	89000225	Initial Release
January 2006	45001/094	89000274	8.1.1.0 Release
April 2012	45001/094	89000730	8.1.6.0 Document
August 2013	45001/094	89000785	8.1.7.0 Release

**© Copyright Retalix, Inc. 1995-2013
All rights reserved**

This publication is protected by federal copyright law. This document and its contents are the proprietary, confidential information and property of Retalix, Inc. ("Retalix"). Unauthorized disclosure, reproduction, distribution or use of this document and/or its contents in any form is strictly prohibited. No part of this publication may be reproduced or transmitted into any human or computer language in any form or by any means, stored in a retrieval system, transmitted, redistributed, translated or disclosed to third parties, or de-compiled in any way including, but not limited to, photocopy, photograph, electronic, mechanical, magnetic or manual without the express written permission of Retalix or its licensors, if any. This document, notwithstanding the above, may be distributed in electronic or printed form to personnel who are employed by either (1) a Retalix customer of the subject system of this document or (2) personnel from an authorized Retalix Channel Partner of the subject system of this document. All copies, so distributed and/or so authorized, shall contain a full copy of this copyright notice.

Retalix has prepared this manual for use by users, authorized third parties and personnel of Retalix as a guide to the proper installation, operation, customization and/or maintenance of Retalix equipment and software. The drawings and specifications contained herein are the property of Retalix and/or its licensors.

Retalix endeavors to ensure that the information in this document is correct and fairly stated but does not accept liability for any error or omission. Retalix makes no representation or warranties with respect to the contents hereof, and specifically disclaims any implied warranties of merchantability or fitness for a particular purpose or non-infringement. No commitments by Retalix or its suppliers are made by or from this documentation which is provided for information only.

Development of Retalix products and documentation is continuous: Retalix reserves the right to revise this publication and to make changes from time to time in the contents hereof or in the products herein described or discussed without notice and without any obligation of Retalix to notify any person or organization of such revision or changes. Information published in this document will likely become obsolete over time and it is recommended that users regularly check for updates and newer versions.

The trademarks Retalix, StoreNext, ISS45, ScanMaster, R10, PocketOffice, RBO, Connected Payments, Connected Services, Connected Loyalty and all other Retalix product names are registered trademarks or trademarks of Retalix; all other trademarks or registered trademarks are the property of their respective owners. Third-party products, services, or company names referenced in this document may be trademarked or copyrighted by their respective owners, and are for identification purposes only. Copyrights, trademarks and license agreements shall be governed and construed in accordance with the laws of the State of Texas and the Federal Arbitration Act, and shall benefit Retalix, its successors, and assigns.

Address comments and corrections to:

Retalix, Inc.
Software Program Director
797 Commonwealth Drive
Warrendale, PA 15086

Table of Contents

Table of Contents	1
Trickle Feed Overview	2
Tf_param.xml File	3
System Parameters	3
Transaction Header	4
Transaction Fields.....	5
Convert Type Table	7
Tail Field	8
Modes for TF Server	8
Reprocess Mode.....	9
Trading Date Identifier	9

Trickle Feed Overview

The ISS45 trickle feed of the transaction file (transact.qdx) allows user defined output files to be created from the current transaction file at timed intervals throughout the day and as part of the EOD process. These files can be either in XML, Ascii or RemaXml format and contain only the transactions and their specific fields as defined to the trickle feed mechanism.

All Trickle Feed parameters and the extracts that determine the contents of the output files will be held in an XML file named c:\pcmaster\tf_param.xml. As defined in this file, transactions will be converted to the selected format and copied to a file located on the local computer (during EOD and/or at a designated time interval).

Trickle feed generated files will include only transactions that belong to complete tickets, or transactions between tickets. A partial ticket will not be converted and an error will be written to c:\pcmaster\log\tf.log.

For control, a Trickle Feed log (c:\pcmaster\log\tf.log) will be updated continuously (with successful writes or errors).

There are different output formats depending on setup or type of file. The name of the output files are as follows:

- EOD file:
 - TREODYYYYMMDD.DAT for Ascii files
 - TREODYYYYMMDD.XML for XML files
 - YYYYMMDD is the working day date
 - Example: TREOD20120123.XML

- Online files:
 - TRPERYYYYMMDDSNNN.DAT for Ascii files
 - TRPERYYYYMMDDSNNN.XML for XML files
 - YYYYMMDD is the working day date, S is serial number (A – Z) NNN – sequence number of file (1 – 999).
 - Example: TRPER20120123A003.DAT, TRPER20120123A001.XML

To assist with verifying the completeness of a full day's transaction file, a file may be created during the End-Of-Day process and include all the transactions for the finished working day. This will aid head-office systems to validate that the whole file has arrived and that a recovery process is not required.

The retailer is responsible for performing the housekeeping of the Trickle Feed files.

Tf_param.xml File

When the services start, the Tf_param.xml file (located in the \PCMASTER folder) is searched. The XML file is the key for the Trickle Feed process. If there is no XML file, or if the **TFinSystem** parameter is set to 0, the Trickle Feed process will not run and the information will be written in the c:\pcmaster\log\tf.log. In the XML the parameters and file contents to be output will be defined as elements.

The parameters can be changed in the XML file or through notepad or another text editor.

The instructions for the conversion and file layout are defined as elements, each with its own attributes. The transactions converted will be based on the data-dictionary stored in the XML file, which define the opcodes to extract and the layout for each opcode.

System Parameters

The system parameter defines how the system works.

```
<TF_Param>
  <SystemParamters>
    <TFInSystem>1</TFInSystem>
    <OutPutFilePath>c:\Pcmaster\Tmp\<</OutPutFilePath>
    <LoopTime>5</LoopTime>
    <Delimiter>,</Delimiter>
    <ConvertType>Xml</ConvertType>
    <CreateEODFile>1</CreateEODFile>
    <CreateOnlineFiles>0</CreateOnlineFiles>
    <NoOfBytesForOutputFiles>0</NoOfBytesForOutputFiles>
  </SystemParamters>
```

Element	Explanation
TFInSystem	Tells if Trickle Feed is enabled within the system or not. Valid values in this element are 1 (enabled) or 0 (disabled).
OutPutFilePath	Sets the path in which the files created will be saved. Can only be a local folder.
LoopTime	Indicates the number of minutes between file generation.
Delimiter	Enables the user to choose the delimiter for the Ascii file. Can have values between 1 and 256 (Ascii characters). The delimiter can be more than one character. If the delimiter is found in a string field, it

Element	Explanation
	will be replaced by a space. Example: the delimiter used is a comma (',') and there is a field that includes a customer name, where a comma divides the first and last names. In this case the comma inside that string will be replaced by a space "Smith, John" will be changed to "Smith John".
ConvertType	Indicates the format of the output file; Ascii or XML. Valid values in this element are Xml, Ascii or RemaXml.
CreateEODFile	If its value is 0 then the EOD file will not be created. Valid values in this element are 0 (disabled) or 1 (enabled).
CreateOnlineFiles	Create online files. Valid values in this element are 0 or 1. If the element value is 1 than online files will be created.
NoOfBytesForOutputFiles	Max size of output file. 0 means no limit to the size of the output file.

Transaction Header

The transaction header defines which op codes will be translated.

```

<TransactionsHeaders>
  <TransactionHeader>
    <Number>1</Number>
    <TrsOpcode>1</TrsOpcode>
    <TrsSubOpcode1>0</TrsSubOpcode1>
    <TrsSubOpcode2>0</TrsSubOpcode2>
    <SubOpcode1Flg>0</SubOpcode1Flg>
    <SubOpcode2Flg>0</SubOpcode2Flg>
    <XmlElementName>PluSale</XmlElementName>
    <Description>Sale Plu Transaction</Description>
    <IgnoreTransaction>0</IgnoreTransaction>
  </TransactionHeader>

```

Element	Explanation
Number	Sequence number that represents the transaction.
TrsOpcode	Transaction opcode to convert. It is 10 base and not Hex value.
TrsSubOpcode1	Transaction sub opcode to convert. It is 10 base and not Hex value.
TrsSubOpcode2	Transaction sub sub opcode to convert. It is 10 base and not Hex value.
SubOpcode1Flg	Allows the option to include the TrsSubOpcode1 as part of the conversion.
SubOpcode2Flg	Allows the option to include the TrsSubOpcode2 as part of the conversion.
XmlElementName	Element name of this transaction.
Description	Description of this transaction.
IgnoreTransaction	Ignores the conversion of this transaction. Valid values in this element are 0 (disabled) or 1 (enabled).

Transaction Fields

The transaction fields define which fields within the opcode will be translated.

```

<TransactionsFields>
  <TransactionField>
    <Number>1</Number>
    <FieldOrder>5</FieldOrder>
    <ConvertType>3</ConvertType>
    <TrsFieldOffset>0</TrsFieldOffset>
    <TrsFieldLength>1</TrsFieldLength>
    <BitsFieldOffset>0</BitsFieldOffset>
    <XmlAttributeName>Opcode</XmlAttributeName>
    <Description>Transaction opcode</Description>
    <IgnoreField>0</IgnoreField>
  </TransactionField>

```

Element	Explanation
Number	Sequence number that represents the transaction.
FieldOrder	The order of the field in the Ascii \ XML output.
ConvertType	The field type (long, short..). See the convert types table below.
TrsFieldOffset	The offset of the field in the transaction.
TrsFieldLength	The length of the field in the transaction. If it contains a bit is is the number of bits within the field.
BitsFieldOffset	The offset of the bit within the byte.
XmlAttributeName	The attribute name that will represent the field in the XML output.
Description	Field description.
IgnoreField	Ignore the conversion of this field. Valid values in this element are 0 (disabled) or 1 (enabled).

Convert Type Table

Value	Convert Type	Remarks
1	Bits to Ascii.	Need to give offset in the byte (values 0 – 7) and the bit number (values 1 – 8).
2	Char to Ascii	
3	Uchar to Ascii	
4	Short to Ascii	
5	Ushort to Ascii	
6	Long to Ascii	
7	Ulong to Ascii	
8	Char[6] to Ascii	
9	Int64 to Ascii	
10	String to Ascii	Need to give field length.
11	Pak date to YYYY-MM-DD	
12	Pak time to HH:MM:SS	
13	Bcd to string	Need to give field length.
14	Add the unique number of date	Used to add an unique working date number. There is no need to define an offset because the data is not taken from the transaction. This field is defined as a tail record.
15	Add store – number untill four digits with leading zeroes.	
16	Add working date	Given either through command line or system

Tail Field

Since the transaction tail fields are valid for all transactions, they only need to be configured once. The configuration is like any other transaction field.

```
<TailFields>
  <TailField>
    <FieldOrder>1</FieldOrder>
    <ConvertType>5</ConvertType>
    <TrsFieldOffset>48</TrsFieldOffset>
    <TrsFieldLength>2</TrsFieldLength>
    <BitsFieldOffset>0</BitsFieldOffset>
    <XmlAttributeName>TicketNumber</XmlAttributeName>
    <Description>Ticket Number</Description>
    <IgnoreField>0</IgnoreField>
  </TailField>
```

Modes for TF Server

The following TF Server modes are either set in a batch file (for example, "TFServer /EOD") or can be enabled when TFServer runs from a command line.

/zero	Resets all pointers within the CMOS file. This is enabled by default in the \PCMASTER\ e-of-day.bat file.
/EOD	Runs on transaction file and creates file for entire day. This is enabled by default in the \PCMASTER\ e-of-day.bat file but must be used in conjunction with the <CreateEODFile>1</CreateEODFile> setting in the Tf_param.xml file.
/service	Every x minutes (defined by Loop Time) information is extracted from the temp file and put in the output file. This command is launched from the SRVSTART.bat and e-of-day.bat files.
/reprocess	Able to run anywhere, but requires a command line The goal of this mode is to reprocess a full TLOG on any PC for support and debug purposes. See the parameters listed below.

Reprocess Mode

The goal of this mode is to reprocess the full TLOG on any PC for support and debug purposes. The command – line is:

```
Tfserver /REPROCESS OUTPUTFILEPATH=c:\pcmaster\tmp\Transact.xml  
INPUTFILEPATH=c:\pcmaster\bak\transact.qdx TV=1 UNIQUE=11  
WORKINGDATE=01/01/2012 STORENUMBER=1234
```

OUTPUTFILEPATH	Path and name of the output file.
INPUTFILEPATH	Path and name of the TLOG file that will be converted.
TV	TV number of the working day of the TLOG. Used to calculate the trading date identifier. If the trading date identifier is not used, any value between 0 and 15 can be used.
UNIQUE	Trading date identifier of the working day of the TLOG. If Trading date identifier is not used any value greater than 15.
WORKINGDATE	Working day of the TLOG
STORENUMBER	Store number

Trading Date Identifier

Since the transaction version number is restarted every 16 days (0 – 15), a non-resettable number is used to identify a day's transaction.

The trading date identifier is kept in the CMOS file (ISS45's file that saves critical information like pointers and flags) and is increased by one every End-of-Day.

The trading date identifier is fully synchronized with the TV number. A validation process is performed every End-of-Day to check that the TV number matches the trading date identifier.

The trading date identifier appears only in the converted output files (trperCCYYMMDDSNNN.dat and treodCCYYMMDD.dat.) according to the definitions in the XML file: the number is in the header of the file and as part of the TAIL in all the transactions.



© Retalix, Inc. 2013

Retalix, Inc. endeavors to ensure that the information in this document is correct and fairly stated but does not accept liability for any error or omission.

The development of Retalix products and services is continuous and published information may not be up to date. It is important to check the current position with Retalix. This document is not part of a contract or license, save insofar as may be expressly agreed.